

N O T I C E

THIS DOCUMENT HAS BEEN REPRODUCED FROM
MICROFICHE. ALTHOUGH IT IS RECOGNIZED THAT
CERTAIN PORTIONS ARE ILLEGIBLE, IT IS BEING RELEASED
IN THE INTEREST OF MAKING AVAILABLE AS MUCH
INFORMATION AS POSSIBLE

"Made available under NASA sponsorship
in the interest of early and wide dis-
semination of Earth Resources Survey
Program information and without liability
for any use made thereof."

8.0-10211

JSC-12917 NASA CR.

160678

FINAL DESIGN SPECIFICATION
FOR
EOD-LARSYS/DATA TRANSFORMATION PROCESSOR MODIFICATION

Job Order 81-127

(TIRF 76-0078)

(E80-10211) FINAL DESIGN SPECIFICATION FOR
EOD-LARSYS/DATA TRANSFORMATION PROCESSOR
MODIFICATION (Lockheed Electronics Co.)
112 P HC A06/MF A01

N80-29790

CSCL 05B

G3/43

Unclas
00211

Prepared By
Lockheed Electronics Company, Inc.
Systems and Services Division
Houston, Texas

Contract NAS 9-15200

For

EARTH OBSERVATIONS DIVISION
SPACE AND LIFE SCIENCES DIRECTORATE




National Aeronautics and Space Administration
LYNDON B. JOHNSON SPACE CENTER

Houston, Texas

April, 1977

LEC-10662



JSC-12917


FINAL DESIGN SPECIFICATION
FOR
EOD-LARSYS/DATA TRANSFORMATION PROCESSOR MODIFICATION
Job Order 81-127
(TIRF 76-0078)

PREPARED BY



J. K. Rowland

APPROVED BY



P. L. Krumm, Supervisor
Software Development Section

Prepared By
Lockheed Electronics Company, Inc.
For
Earth Observations Division
NATIONAL AERONAUTICS AND SPACE ADMINISTRATION
LYNDON B. JOHNSON SPACE CENTER
HOUSTON, TEXAS
April, 1977

LEC-10662

CONTENTS

| Section | Page |
|--|------|
| 1. SCOPE | 1-1 |
| 2. APPLICABLE DOCUMENTS. | 2-1 |
| 3. SYSTEM DESCRIPTION. | 3-1 |
| 3.1 <u>HARDWARE DESCRIPTION</u> | 3-1 |
| 3.2 <u>SOFTWARE DESCRIPTION</u> | 3-1 |
| 3.2.1 SOFTWARE COMPONENT NO. 1 (DATATR). | 3-2 |
| 3.2.2 SOFTWARE COMPONENT NO. 2 (SETUP8). | 3-3 |
| 3.2.3 SOFTWARE COMPONENT NO. 3 (SETREM). | 3-4 |
| 3.2.4 SOFTWARE COMPONENT NO. 4 (TRHIST). | 3-6 |
| 3.2.5 SOFTWARE COMPONENT NO. 5 (LNTRAN). | 3-8 |
| 3.2.6 SOFTWARE COMPONENT NO. 6 (TRANSF). | 3-10 |
| 4. OPERATION | 4-1 |
| 4.1 <u>USER DOCUMENTATION</u> | 4-1 |
| 5. TEST PROCEDURE. | 5-1 |
| 5.1 <u>DESCRIPTION OF TESTS</u> | 5-1 |
| Appendix | |
| A. DATA TRANSFORMATION FLOWCHART | A-1 |
| B. LISTINGS. | B-1 |
| C. VERIFICATION RUNS | C-1 |

1. SCOPE

1.1 GENERAL

This specification establishes the design specifications and describes modifications made to the Data Transformation processor of the EOD-LARSYS system to satisfy the requirements specified on the IDSD category 1 (Job Order 81-127) task agreement titled, "Data Transformation Program Modification", dated 6/11/76. The EOD-FCMO reference for the task is TIRF (Transmittal Information Request Form) 76-0078.

2. APPLICABLE DOCUMENTS

The following documents, of exact issue shown, form a part of this specification to the extent specified herein:

- EOD-LARSYS Users Document: LEC 3984 Revision II
- Task Description and Agreement, dated 6/17/76, "Data Transformation Program Modification"
- EOD-FCMO TIRF 76-0078

3. SYSTEM DESCRIPTION

3.1 HARDWARE DESCRIPTION

N/A

3.2 SOFTWARE DESCRIPTION

The Data Transformation processor of the EOD-LARSYS system is modified to include an optional additive transformation bias vector, optional input and application of scaling parameters, to allow the scaling parameters used by the processor to be output on punched cards in processor control card format, and to allow for a transformation matrix with up to sixteen (16) linear combinations (i.e., up to 16×30 transformation matrix).

The application of the input transformation matrix was removed from subroutine LNTRAN and TRHIST and replaced with a subroutine called TRANSF, which implements the transformation of the input data vectors. The optional input transformation bias vector is incorporated in the transformation implemented in TRANSF.

Previously all transformed data values were arbitrarily scaled to a range of 0-256. This procedure has been changed so that no rescaling will be applied unless a processor control card, "RESCALE", is input directing the processor to scale the transformed data to a range 0-255. If scaling is requested, either the same (histogram or statistical) procedures as before are used for scaling or the scaling parameters are input to the processor by an "OPTION SCAFAC" control card.

The "OPTION PUNCH" processor control card initiates the punched card output of the scaling parameters used by the processor. These scaling parameters may be used as input in subsequent runs, without modification to the card(s).

3.2.1 SOFTWARE COMPONENT NO. 1 (DATATR)

3.2.1.1 Linkages

DATATR is the driver program for Data Transformation processing and is called by MONTOR, the LARSYS executive program. DATATR may call SETUP8, SETREM, KBTRAN, MAXMAT, TRHIST, or LNTRAN during processing.

3.2.1.2 Interfaces

DATATR utilizes common blocks GLOBAL, INFORM, and TRBLCK.

3.2.1.3 Inputs

Calling arguments unchanged in DATATR.

3.2.1.4 Outputs

None

3.2.1.5 Storage Requirements

Storage used: Code - 167₈, Data - 4171₈

3.2.1.6 Description

DATATR controls the Data Transformation processing. To determine which options are to be exercised during processing, SETUP8 is called to read the Processor Control Cards. If scaling parameters are input by control cards, SETREM is called to initialize the arrays CON and MIN with the scaling parameters from the input scale parameter pairs. The processing continues with a call to LNTRAN, where the data is transformed. (See section 3.2.6.6 for equation) If rescaling is desired by the statistical method, the histogram method, or the user input of parameters method, the processing continues with either a call to KBTRAN for the statistical method, to TRHIST for the histogram method, or to LNTRAN for the user-input method.

If rescaling is not specifically requested by means of the RESCALE control card, no rescaling of transformed data values will be performed.

3.2.1.7 Flowchart

See Appendix A

3.2.1.8 Listings

See Appendix B.

3.2.2 SOFTWARE COMPONENT NO. 2 (SETUP8)

3.2.2.1 Linkages

SETUP8 is called from DATATR. In the process of reading control cards, SETUP8 may call NXTCHR, FIND, BMFIL, NUMBER, ORDER, CRDSTA, FLTNUM, REDSAV, PRTCov, or WRTBM.

3.2.2.2 Interfaces

SETUP8 utilizes common blocks GLOBAL, INFORM, and TRBLCK.

3.2.2.3 Inputs

Additions to or modification of the input to the SETUP8 subroutine that result from this data transformation processor modification are the control cards OPTION PUNCH, OPTION SCAFAC, BIAS, and RESCALE. Control card formats are described in section 4.1, User Documentation.

3.2.2.4 Outputs

SETUP8 outputs a line printer summary of the control card input. Input parameters or processing flags as a result of the OPTION PUNCH, OPTION SCAFAC, BIAS, or RESCALE control cards are returned to DATATR by subroutine argument.

3.2.2.5 Storage Requirements

Storage used: Code - 1372₈, Data - 303₈

3.2.2.6 Description

SETUP8 reads and analyzes all input processor control cards, including any parameter values provided on the control cards and sets default values for Data Transformation. Defaults added as a result of this specification are: (1) the additive transformation bias vector is set = 0 if no BIAS control card is provided, and (2) transformed data rescaling is not performed if the RESCALE control card is not input.

3.2.2.7 Flowchart

See Appendix A.

3.2.2.8 Listings

See Appendix B.

3.2.3 SOFTWARE COMPONENT NO. 3 (SETREM)

3.2.3.1 Linkages

SETREM is called from DATATR. A Univac system program, CMERR, is called by SETREM, to provide an error exit if encountered with scale parameters read from the OPTION SCAFAC control card.

3.2.3.2 Interfaces

Communication with DATATR is accomplished via calling arguments.

3.2.3.3 Inputs

The inputs to the SETREM subroutine (via calling argument) are the scale parameters read from the OPTION SCAFAC control card(s).

The scaling parameters are ordered pairs on the OPTION SCAFAC control card. Each pair is associated with one component of the transformed data. The first value in each pair is the multiplicative factor, and the second value in each pair is the transformed data minimum "M". These scaling parameter pairs are used in LNTRAN to scale the transformed data to the range of 0-255.

3.2.3.4 Outputs

SETREM outputs the scaling parameters to DATATR via subroutine arguments, CON and MIN (with $CON_i = S_i$ and $MIN_i = M_i$; see the description of the OPTION SCAFAC card, section 4.1).

3.2.3.5 Storage Requirements

Storage used: Code - 75_8 , Data - 107_8

3.2.3.6 Description

SETREM receives the input scale parameters from DATATR in a single array (CONMIN) as they have been read from OPTION SCAFAC control card(s) in SETUP8. Since the input scale parameters consist of two values - the scaling factor, S (=CON), and the additive scaling bias, M (=MIN) - these values must be unpacked from the input array and stored in the CON and MIN arrays for use by LNTRAN. SETREM checks to see that there is one-for-one correspondence between input scaling parameter pairs and the components of the transformation. If the test for input pair versus transformation component fails due to too many or too few input scale parameter pairs, an error message is printed and Data Transformation is terminated by SETREM. The error message returned by SETREM is:

"SETREM ERROR - THERE WERE XX SCALE FACTORS AND MINIMUM VALUES INPUT THROUGH SCAFAC OPTION. YY LINEAR COMBINATIONS WERE REQUESTED. THERE MUST BE A SCALE FACTOR AND A MINIMUM VALUE FOR EACH LINEAR COMBINATION. THE PROGRAM WILL TERMINATE THROUGH CMERR."

3.2.3.7 Detailed Flowcharts

See Appendix A.

3.2.3.8 Listings

See Appendix B.

3.2.4 SOFTWARE COMPONENT NO. 4 (TRHIST)

3.2.4.1 Linkages

TRHIST is called from DATATR. TRHIST calls TAPHDR, FSBSFL, LAREAD, FLDINT, LINERD, FLDINT, and TRANSF.

3.2.4.2 Interfaces

TRHIST utilizes common blocks GLOBAL, INFORM, and TRBLCK.

3.2.4.3 Inputs

Input that affects TRHIST is the additive transformation bias vector input via the BIAS control card, and used in the transformation of data as $Ax+b$, where A = the transformation matrix, x = data, and b = bias value from the input BIAS control card. The input bias vector is transmitted to TRHIST via a calling argument, BIAS, added as a result of these modifications.

3.2.4.4 Outputs

There is no change in TRHIST output resulting from this specification.

3.2.4.5 Storage Requirements

Storage used: Code - 744₈, Data - 204₈

3.2.4.6 Description

The function performed by TRHIST is to compute scaling parameters for the transformed data, using a histogram of the transformed data to derive the scaling parameters MAX, MIN, and CON. A histogram of a segment of the transformed image is performed to find the maximum value, MAX_i , and minimum value, MIN_i , for each component of the transformed data. The scale factor, CON_i , is computed as $255/(MAX_i - MIN_i)$. The input (or default) PEROUT is applied in TRHIST in obtaining the scaling parameters MAX, MIN, and CON.

If the user defined field is smaller than 2000 pixels, all pixels are used in the histogram. Otherwise the following formula is used to determine the line increment and sample increment needed to obtain 2000 points for the histogram:

$$\alpha = \left(\frac{M \cdot N}{2000} \right)^{1/2}$$

where M = Number of samples per line

N = Number of lines

α = increment (integer)

The input additive transformation bias vector is passed to TRHIST by subroutine argument (BIAS) and is used in TRANSF, which is called by TRHIST, to provide the transformation $Ax+b$, with A = the transformation matrix, x = data vector, and b = transformation bias vector.

The function performed by TRHIST is invoked by the input RESCALE control card when neither of the other two options for rescaling (statistical and user-input) are specified.

3.2.4.7 Flowchart

See Appendix A.

3.2.4.8 Listings

See Appendix B.

3.2.5 SOFTWARE COMPONENT NO. 5 (LNTRAN)

3.2.5.1 Linkages

LNTRAN is called from DATATR. During its processing LNTRAN calls LARSYS routines TAPHDR, FSBSFL, LAREAD, FLDINT, WRTHDR, LINERD, FLDINT, TRANSF, WRTLIN, and COMHST and UNIVAC system routine NTRAN.

3.2.5.2 Interfaces

LNTRAN utilizes common blocks GLOBAL, INFORM, and TRBLCK.

3.2.5.3 Inputs

Additional calling argument input to the LNTRAN routine due to these modifications include the scaling flags (RESCAL and SCAFLG) the punch card flag (NPUN), the transformation bias values (BIAS), and the flag SCAFLG set to indicate the source of the scaling parameters MAX, MIN, and CON (SCAFLG = 1; histogram, SCAFLG = 2; statistical; SCAFLG = 3, user-input).

3.2.5.4 Outputs

The transformed data set is output on UNIVAC Unit L (Fortran Unit 14) as usual. This assignment must be made to tape, if the transformed data set is to be saved by the user. The output transformed data set file will be in one of two formats, as specified on the FORMAT control card.

3.2.5.5 Storage Requirements

Storage used: Code - 2130₈, Data - 17477₈

3.2.5.6 Description

The functions provided by LNTRAN are to initiate the transformation of the data by a call to TRANSF, to rescale the transformed data, histogram the transformed data, apply PEROUT to the distribution of the transformed data, and output that data to a file, TRFORM. Depending on the flag, RESCAL, the transformed data may be either rescaled to 0-255 range or output to the file unscaled as it is received from the transformation subroutine, TRANSF. If rescaling is not performed (RESCAL = 0) the transformed values are checked for being within the range 0-255. Any value outside the range are set to the range minimum or maximum (0-255).

If the transformed data is to be rescaled (RESCAL > 0), rescaling is performed in LNTRAN using the following equation:

$$Y_i = \text{CON}_i (X_{T_i} - \text{MIN}_i) \quad \text{for each component } i \text{ of the transformed data vector}$$

where

MIN_i = minimum value for component i

X_{T_i} = transformed data point

$\text{CON}_i = 255 / (\text{MAX}_i - \text{MIN}_i)$

Y_i = rescaled transformed data point

If the OPTION PUNCH control card has been input, LNTRAN will output to the system punch file the card images containing the scaling parameters used to rescale the transformed data. The punched cards will be in control card format (OPTION SCAFAC=) and each card will contain two pairs of scaling parameters (CON, MIN). Each pair is associated with one component of the transformed data.

3.2.5.7 Detailed Flowcharts

See Appendix A.

3.2.5.8 Listings

See Appendix B.

3.2.6 SOFTWARE COMPONENT NO. 6 (TRANSF)

3.2.6.1 Linkages

TRANSF is called from both TRHIST and LNTRAN.

3.2.6.2 Interfaces

TRANSF utilizes common block TRBLCK.

3.2.6.3 Inputs

TRANSF receives the tape-input pixels, the transformation bias vector, the transformation matrix, and other parameters it needs to utilize this information via subroutine argument and the common block TRBLCK. The transformation bias vector is input to the processor, then to TRANSF, via the BIAS control card. The transformation matrix is input to the processor, then to TRANSF, via the B-MATRIX control card. The BIAS control card is discussed in section 4.0 below. The B-MATRIX control card is discussed in the EOD-LARSYS User Document, LEC-3984.

3.2.6.4 Outputs

TRANSF returns the transformed data value argument to LNTRAN (or TRHIST).

3.2.6.5 Storage Requirements

Storage used: Code 122₈, Data 34₈

3.2.6.6 Description

TRANSF performs the following linear transformation:

$$\vec{Z} = A\vec{X}$$

or, optionally,

$$\vec{Z} = A\vec{X} + \vec{b}$$

where

\vec{Z} = transformed data vector

A = transformation matrix; either the B-Matrix or a user-supplied transformation matrix

\vec{X} = input data vector

\vec{b} = an additive bias vector

The B-Matrix is a dimension reduction transformation generated by the SELECT processor in EOD-LARSYS. The B-Matrix may be input to DATA-TR either from a file or a card deck created by the SELECT processor.

A user-supplied transformation matrix must be input in the same format as the B-Matrix. The format of the input transformation matrix is described in section 3.0 of the EOD-LARSYS USERS DOCUMENT, LEC-3984.

For the transformation, $\vec{Z} = A\vec{X} + \vec{b}$, the bias vector, \vec{b} , is an option to the user. The option is exercised and the bias vector is input via the BIAS control card. TRANSF performs the data transformation, $\vec{Z} = A\vec{X}$, in the absence of the BIAS control card.

3.2.6.7 Detailed Flowcharts

See Appendix A.

3.2.6.8 Listings

See Appendix B.

4. OPERATION

The following section describes the Data Transformation processor as modified per this specification and the processor control cards added or revised due to this modification. Operation of the Data Transformation processor, utilizing the changes described in this specification, is accomplished by use of processor control cards as described below.

4.1 USER DOCUMENTATION

The following table contains the options that affect this specification, in the form of the processor control cards which are added or modified to initiate the design specification. The format of these control cards are standard EOD-LARSYS format; i.e., the keyword must begin in card column 1, the parameter(s) must begin in or after column 11 and end in or before card column 72:

| <u>KEYWORD</u> | <u>PARAMETER(S)</u> | <u>FUNCTION</u> |
|----------------|--|--|
| RESCALE | None (DEFAULT: No rescaling performed) | Initiates rescaling of the transformed data set to an integer range, 0-255. No parameters are input on this card. The method of rescaling will depend either on use of another control card to indicate the type of rescaling (statistical or user-input) to be performed, or defaulting to the histogram method if another option is not input. |

KEYWORDPARAMETER(S)FUNCTION

OPTION

SCAFAC=(S_1, M_1),
(S_2, M_2), ..., (S_N, M_N)
N=1, No. components
of \vec{Z}
(DEFAULT: Histogram
method of rescaling)

Initiates the use of input scaling parameters, (S_i, M_i), to be used in rescaling the transformed data set to a range of 0-255. The scale parameters are ordered to be in correspondence with the \vec{Z} (transformed data) components which they are to be applied to. Each pair of scaling parameters is:
 S_i =scale factor for component i
 $=255/(\text{MAX}_i - \text{MIN}_i)$
 M_i =minimum of component i.
 S_i and M_i are decimal (floating point) numbers used as:
 $Y_i = S_i (\vec{Z}_i - M_i)$, where Y_i is the rescaled transformed \vec{Z} , component i. The enclosing parenthesis, "(" and ")", and the separating comma, ",", are required for each pair of scaling parameters. The scaling parameter pairs are also separated by the comma, ",". Blanks are ignored on the card. Continuation of a list of scaling parameters is accomplished by repeating the OPTION SCAFAC= card, with the list of pairs continuing from the preceding OPTION SCAFAC= card.

KEYWORDPARAMETER(S)FUNCTION

BIAS

b_1, b_2, \dots, b_k
or
 $N * b_1, b_{i+1}, \dots$
 k =NO. of components
in the transformed
data set
 N =an integer repetition
factor for b_i
(DEFAULT: $b_i = 0.0$
 $i = 1, \dots, 16$)

b_i are decimal (floating
point) numbers, separated
by a comma, ",", which
comprise the bias vector
to be applied in the
transformation of the
input data set:

$$\vec{Z} = A \vec{X} + \vec{b}$$

OPTION

PUNCH

(DEFAULT: no punched
output scaling para-
meters)

Directs the program to out-
put punched cards containing
the scaling parameters,
(S_I, M_I), which were used to
rescale the transformed data
set.

NOTE: If PEROUT > 0, the out-
put scaling parameters reflect
the range of the transformed
data after application of
PEROUT.

5. TEST PROCEDURE

5.1 DESCRIPTION OF TESTS

Five runs of the modified data transformation processor will be used to verify the output of the processor. The output from each of the five test runs is contained in Appendix C. TEST RUN 1 is headed by "SAMPLE RUN NO. 1", TEST RUN 2 is headed by "SAMPLE RUN NO. 7", TEST RUN 3 is headed by "SAMPLE RUN NO. 2", TEST RUN 4 is headed by "SAMPLE RUN NO. 5", and TEST RUN 5 is headed by "SAMPLE RUN 6". In all test runs, the transformation matrix following the "B-MATRIX CARDS" control card is a unit matrix.

TEST RUN 1 illustrates the default no-reading option (no "RESCALE" control card input), with no distribution truncation (PEROUT=0), and no bias applied to the transformed values (BIAS=[0]). With the unit transformation matrix applied, the histogram for each of the four components reflects the actual data values in each of the four channels.

TEST RUN 2 is the same as TEST RUN 1, except a selective additive bias is applied to the transformed data. Components 1 and 3 have no bias applied and the transformed values of components 2 and 4 are biased by +100 and -100, respectively. The histograms for this run illustrate the results of application of a transformation bias which is input via the "BIAS" control card.

TEST RUN 3 illustrates the results from the statistical rescaling option ("MODULE" and/or "STATFILE" control cards), with the initial range of transformed values constrained to be within 2 sigma (LAM=2) of the mean of each component, and the final output transformed values constrained to be within the central 90% of the distribution of the initial transformed values (PEROUT=5).

The histogram of each component of the final output transformed/rescaled values will be compared for agreement with results from the unmodified data transformation processor, using the statistical rescale method. The histograms should be identical, except for allowance for the slight difference in scaling parameters due to the fact that the unmodified processor computed a scaling factor based on a range of 0-256, and the modified processor computes a scaling factor based on a range 0-255. TEST RUN 3 also exercises the option of punching the scaling parameters ("OPTION PUNCH") computed and applied in the run. The punched cards from this run will be input in TEST RUN 4.

TEST RUN 4 illustrates rescaling of transformed values with user-input scaling parameters ("OPTION SCAFAC=XX.X, ...").

The input scaling parameters are on processor control cards punched in TEST RUN 3. The histograms for TEST RUN 3 and TEST RUN 4 will be compared for agreement. The results should be identical, except for slight differences due to round-off of the input scaling parameters to three decimal places, compared to the eight decimal place values internally computed and applied in TEST RUN 3.

TEST RUN 5 illustrates rescaling by the histogram method. The histograms will be compared with histograms from the unmodified processor using the histogram rescale method. The histogram should be identical, except for slight differences reflected by the change of rescaled value range from 0-256 in the unmodified processor to a range 0-255 in the modified processor.

TEST VERIFICATION

For Data Transformation Program Modification

This verification is being conducted to insure that the delivered program products satisfy the requirements as originally stated by the requesting organization.

M C Trichel
NASA Monitor

J. C. Minter
Requestor

Developer

Barbara Mills
Cognizant System Manager


Quality Assurance
C. J. Anderson
Test Conductor


Verification Date: 4/25/77

APPENDIX A
DATA TRANSFORMATION FLOWCHART

FUNCTIONAL FLOW CHART
DATA-TR PROCESSOR

PAGE 1



ORIGINAL PAGE 1.
OF POOR QUALITYORIGINAL PAGE IS
OF POOR QUALITY



APPENDIX B

LISTINGS

221 92

09 MAY 77

FOR DATATR.DATATR
UNIVAC 1100 FONTMAY V EXEC 11 LEVEL 25A - (EXEC LEVEL 612010010A)
THIS COMPILATION WAS DONE ON 09 MAY 72 AT 2210130

SUBROUTINE DATATR ENTRY POINT 000257

STORAGE USED: CODE(1) 000302T DATA(0) 0045031 BLANK COMMON(2) 000000

COMMON BLOCKS:

0003 INTRM 001154
0004 INBLCK 000076
0005 GLOBAL 000075

EXTERNAL REFERENCES (BLOCK, NAME)

0006 SETUPB
0007 SETHEM
0010 ABTRAM
0011 NAMAT
0012 TANTIST
0013 LNTMAN
0014 MNUUS
0015 NI02S
0016 MEMK3S

STORAGE ASSIGNMENT (BLOCK, TYPE, RELATIVE LOCATION, NAME)

| | | | | | | | | | | | | | | |
|------|--------|--------|------|--------|--------|--------|--------|--------|-------|--------|--------|--------|--------|--------|
| 0001 | 000002 | 1236 | 0001 | 000232 | 1636 | 0001 | 000077 | 20L | 0001 | 000112 | 30L | 000197 | 30L | |
| 0001 | 000000 | 00L | 0000 | 004445 | 00F | 0000 | 001198 | ACOM | 0000 | 001437 | ADUMYM | 000100 | ANAX | |
| 0000 | R | 001120 | AMIN | 0000 | 000073 | ASAV | 0000 | ASAVFL | 0000 | 000000 | AVAR2 | 000010 | 0145 | |
| 0000 | R | 000060 | 0MAT | 0000 | 000055 | 0HFILE | 0000 | 000056 | 0HKEY | 0000 | 001431 | 0HNIK6 | 000010 | CL5102 |

ORIGINAL PAGE IS
OF POOR QUALITY

```

00101 10 C SUBROUTINE DATATN(ARRAY, TOP)
00102 20 C
00103 30 C IMPLICIT INTEGER(A-Z)
00104 40 C
00105 50 C
00106 60 C
00107 70 C
00108 80 C
00109 90 C
00110 100 C
00111 110 C
00112 120 C
00113 130 C
00114 140 C
00115 150 C
00116 160 C
00117 170 C
00118 180 C
00119 190 C
00120 200 C
00121 210 C
00122 220 C
00123 230 C
00124 240 C
00125 250 C
00126 260 C
00127 270 C

```

```

00101 10 C SUBROUTINE DATATN(ARRAY, TOP)
00102 20 C
00103 30 C IMPLICIT INTEGER(A-Z)
00104 40 C
00105 50 C
00106 60 C
00107 70 C
00108 80 C
00109 90 C
00110 100 C
00111 110 C
00112 120 C
00113 130 C
00114 140 C
00115 150 C
00116 160 C
00117 170 C
00118 180 C
00119 190 C
00120 200 C
00121 210 C
00122 220 C
00123 230 C
00124 240 C
00125 250 C
00126 260 C
00127 270 C

```

```

00101 10 C SUBROUTINE DATATN(ARRAY, TOP)
00102 20 C
00103 30 C IMPLICIT INTEGER(A-Z)
00104 40 C
00105 50 C
00106 60 C
00107 70 C
00108 80 C
00109 90 C
00110 100 C
00111 110 C
00112 120 C
00113 130 C
00114 140 C
00115 150 C
00116 160 C
00117 170 C
00118 180 C
00119 190 C
00120 200 C
00121 210 C
00122 220 C
00123 230 C
00124 240 C
00125 250 C
00126 260 C
00127 270 C

```

ORIGINAL PAGE IS
OF POOR QUALITY

```
00127 260 IF THE FLAG RESCAL IS ZERO, NO RESCALING OCCURS
00128 270
00129 280
00130 290
00131 300
00132 310
00133 320
00134 330
00135 340
00136 350
00137 360
00138 370
00139 380
00140 390
00141 400
00142 410
00143 420
00144 430
00145 440
00146 450
00147 460
00148 470
00149 480
00150 490
00151 500
00152 510
00153 520
00154 530
00155 540
00156 550
00157 560
00158 570
00159 580
00160 590
00161 600
00162 610
00163 620
00164 630
00165 640
00166 650
00167 660
00168 670
00169 680
00170 690
00171 700
00172 710
00173 720
00174 730
00175 740
00176 750
00177 760
00178 770
00179 780
00180 790
00181 800
00182 810
00183 820
00184 830
00185 840
00186 850
00187 860
00188 870
00189 880
00190 890
00191 900
00192 910
00193 920
00194 930
00195 940
00196 950
00197 960
00198 970
00199 980
00200 990
```

```
00127 500 IF (SCALF6.EQ.1) GO TO 30
00128 510
00129 520
00130 530
00131 540
00132 550
00133 560
00134 570
00135 580
00136 590
00137 600
00138 610
00139 620
00140 630
00141 640
00142 650
00143 660
00144 670
00145 680
00146 690
00147 700
00148 710
00149 720
00150 730
00151 740
00152 750
00153 760
00154 770
00155 780
00156 790
00157 800
00158 810
00159 820
00160 830
00161 840
00162 850
00163 860
00164 870
00165 880
00166 890
00167 900
00168 910
00169 920
00170 930
00171 940
00172 950
00173 960
00174 970
00175 980
00176 990
```


FOR SETUP8 SETUP8 EXEC 11 LEVEL 25A -JERECO LEVEL E12010010A1 221-91
UNIVAC 1108 FORTRAN WAS DONE ON 09 MAY 77 AT 22:09:38

SUBROUTINE SETUP8 ENTRY POINT 001456

STORAGE USED: CODE(11) 001557; DATA(8) 0004041; BLANK COMMON(12) 000000

COMMON BLOCKS:

0003 INFORM 001155
0004 GLOBAL 000075
0005 INBLCK 000046

EXTERNAL REFERENCES (BLOCK, NAME)

0006 MATCHR
0007 FIND
0010 WFFIL
0011 NUMBER
0012 ORDEM
0013 PLTNUM
0014 CROSTA
0015 MEDSAV
0016 PATCUV
0017 SHTRM
0020 MRUUS
0021 NI015
0022 NI025
0023 MRUUS
0024 MEMK25
0025 MEMK35

[illegible]

```

00101 SUBROUTINE SETUPBHMAT,L,COMB,BMTRIG,PEXOUT,MAKPT,AKRAY,LAM,SCALE,  S000U2
00102 TOP, TRANSF, RESCAL, BIAS, ADDNUM, COMMIN, NPUM,  SET000U2
00103 C
00104 IMPLICIT INTEGER(*-2)
00105 REAL COMMIN(32), BIAS(16), WMAT(90)
00106 DIMENSION MAKPT(30),
00107 DIMENSION AKMAT(1),
00108 DIMENSION EQUVEC(2)
00109 C
00110 INCLUDE COMBK1.LIST
00111 COMMON,INFUM,NOLCS2,NOSUM2,NOFET2,VARSZ,TOTVT2,NOFL02,
00112 AVANZ,COVANZ,CLSID2,SUBNU2,SUBUSZ,FLOSZ,VERTK2,
00113 FETVZ(30),SUBVZ(75),SUBPH(75),CLSVZ(60),
00114 KPTVZ(60),NUGRP,GRPMAN(60),CMPDEX(61),
00115 GHPCHK(61),GROUPS(124)

```


| LINE NO. | STATEMENT | INITIAL STATE |
|----------|---|---------------|
| 100 | INITIALIZE THE TRANSFORMATION BIAS VECTOR (BIAS) AND NO. OF BIAS VALUES (NBS) | BIAS = 0 |
| 101 | DO 10 I=1,NBS | |
| 102 | BIAS(I) = U.O | |
| 103 | NBS = 0 | |
| 104 | NUDTAP = .FALSE. | |
| 105 | NUDTIL = .FALSE. | |
| 106 | NUSTAP = .FALSE. | |
| 107 | NUSEIL = .FALSE. | |
| 108 | NUSTAP = .FALSE. | |
| 109 | NUSEIL = .FALSE. | |
| 110 | NUSTAP = .FALSE. | |
| 111 | NUSEIL = .FALSE. | |
| 112 | NUSTAP = .FALSE. | |
| 113 | NUSEIL = .FALSE. | |
| 114 | NUSTAP = .FALSE. | |
| 115 | NUSEIL = .FALSE. | |
| 116 | NUSTAP = .FALSE. | |
| 117 | NUSEIL = .FALSE. | |
| 118 | NUSTAP = .FALSE. | |
| 119 | NUSEIL = .FALSE. | |
| 120 | NUSTAP = .FALSE. | |
| 121 | NUSEIL = .FALSE. | |
| 122 | NUSTAP = .FALSE. | |
| 123 | NUSEIL = .FALSE. | |
| 124 | NUSTAP = .FALSE. | |
| 125 | NUSEIL = .FALSE. | |
| 126 | NUSTAP = .FALSE. | |
| 127 | NUSEIL = .FALSE. | |
| 128 | NUSTAP = .FALSE. | |
| 129 | NUSEIL = .FALSE. | |
| 130 | NUSTAP = .FALSE. | |
| 131 | NUSEIL = .FALSE. | |
| 132 | NUSTAP = .FALSE. | |
| 133 | NUSEIL = .FALSE. | |
| 134 | NUSTAP = .FALSE. | |
| 135 | NUSEIL = .FALSE. | |
| 136 | NUSTAP = .FALSE. | |
| 137 | NUSEIL = .FALSE. | |
| 138 | NUSTAP = .FALSE. | |
| 139 | NUSEIL = .FALSE. | |
| 140 | NUSTAP = .FALSE. | |
| 141 | NUSEIL = .FALSE. | |
| 142 | NUSTAP = .FALSE. | |
| 143 | NUSEIL = .FALSE. | |
| 144 | NUSTAP = .FALSE. | |
| 145 | NUSEIL = .FALSE. | |
| 146 | NUSTAP = .FALSE. | |
| 147 | NUSEIL = .FALSE. | |
| 148 | NUSTAP = .FALSE. | |
| 149 | NUSEIL = .FALSE. | |
| 150 | NUSTAP = .FALSE. | |
| 151 | NUSEIL = .FALSE. | |
| 152 | NUSTAP = .FALSE. | |
| 153 | NUSEIL = .FALSE. | |
| 154 | NUSTAP = .FALSE. | |
| 155 | NUSEIL = .FALSE. | |
| 156 | NUSTAP = .FALSE. | |
| 157 | NUSEIL = .FALSE. | |
| 158 | NUSTAP = .FALSE. | |
| 159 | NUSEIL = .FALSE. | |
| 160 | NUSTAP = .FALSE. | |
| 161 | NUSEIL = .FALSE. | |
| 162 | NUSTAP = .FALSE. | |
| 163 | NUSEIL = .FALSE. | |
| 164 | NUSTAP = .FALSE. | |
| 165 | NUSEIL = .FALSE. | |
| 166 | NUSTAP = .FALSE. | |
| 167 | NUSEIL = .FALSE. | |
| 168 | NUSTAP = .FALSE. | |
| 169 | NUSEIL = .FALSE. | |
| 170 | NUSTAP = .FALSE. | |
| 171 | NUSEIL = .FALSE. | |
| 172 | NUSTAP = .FALSE. | |
| 173 | NUSEIL = .FALSE. | |
| 174 | NUSTAP = .FALSE. | |
| 175 | NUSEIL = .FALSE. | |
| 176 | NUSTAP = .FALSE. | |
| 177 | NUSEIL = .FALSE. | |
| 178 | NUSTAP = .FALSE. | |
| 179 | NUSEIL = .FALSE. | |
| 180 | NUSTAP = .FALSE. | |
| 181 | NUSEIL = .FALSE. | |
| 182 | NUSTAP = .FALSE. | |
| 183 | NUSEIL = .FALSE. | |
| 184 | NUSTAP = .FALSE. | |
| 185 | NUSEIL = .FALSE. | |
| 186 | NUSTAP = .FALSE. | |
| 187 | NUSEIL = .FALSE. | |
| 188 | NUSTAP = .FALSE. | |
| 189 | NUSEIL = .FALSE. | |
| 190 | NUSTAP = .FALSE. | |
| 191 | NUSEIL = .FALSE. | |
| 192 | NUSTAP = .FALSE. | |
| 193 | NUSEIL = .FALSE. | |
| 194 | NUSTAP = .FALSE. | |
| 195 | NUSEIL = .FALSE. | |
| 196 | NUSTAP = .FALSE. | |
| 197 | NUSEIL = .FALSE. | |
| 198 | NUSTAP = .FALSE. | |
| 199 | NUSEIL = .FALSE. | |
| 200 | NUSTAP = .FALSE. | |
| 201 | NUSEIL = .FALSE. | |
| 202 | NUSTAP = .FALSE. | |
| 203 | NUSEIL = .FALSE. | |
| 204 | NUSTAP = .FALSE. | |
| 205 | NUSEIL = .FALSE. | |
| 206 | NUSTAP = .FALSE. | |
| 207 | NUSEIL = .FALSE. | |
| 208 | NUSTAP = .FALSE. | |
| 209 | NUSEIL = .FALSE. | |
| 210 | NUSTAP = .FALSE. | |
| 211 | NUSEIL = .FALSE. | |
| 212 | NUSTAP = .FALSE. | |
| 213 | NUSEIL = .FALSE. | |
| 214 | NUSTAP = .FALSE. | |
| 215 | NUSEIL = .FALSE. | |
| 216 | NUSTAP = .FALSE. | |
| 217 | NUSEIL = .FALSE. | |
| 218 | NUSTAP = .FALSE. | |
| 219 | NUSEIL = .FALSE. | |
| 220 | NUSTAP = .FALSE. | |
| 221 | NUSEIL = .FALSE. | |

| 00211 | PEROUT=5 | |
|-------|----------|--|
| 00211 | C | INITIALIZE THE HEADING FOR UNTRANSFORMED STATISTICS PRINTOUT |
| 00212 | C | |
| 00213 | | COVMD111) = 6M * .01 |
| 00214 | | COVMD121) = 6M * .01 |
| 00215 | | COVMD131) = 6M * .01 |
| 00216 | | COVMD141) = 6M * .01 |
| 00217 | | DO 30 I=1,10 |
| 00222 | C | 30 COVMD111) = BLANK |
| 00223 | | |
| 00224 | C | 40 COVMD111) = BLANK |
| 00225 | | |
| 00226 | C | 50 COL=0 |
| 00227 | | IF INUS1AP .OM. NUS1FL1 SCALE=2 D STATEFILE ZARD' READ * |
| 00228 | | READ 15,60 CODE=CARDZ |
| 00229 | | 60 FORMAT(16,X,62A1) |
| 00230 | | 70 FORMAT(12,70 CODE=CARDZ |
| 00231 | | 80 IF (1,1) .OM. MAX |
| 00232 | | 90 IF (1,1) .OM. MAX |
| 00233 | | 100 IF (1,1) .OM. MAX |
| 00234 | | 110 IF (1,1) .OM. MAX |
| 00235 | | 120 IF (1,1) .OM. MAX |
| 00236 | | 130 IF (1,1) .OM. MAX |
| 00237 | | 140 IF (1,1) .OM. MAX |
| 00238 | | 150 IF (1,1) .OM. MAX |
| 00239 | | 160 IF (1,1) .OM. MAX |
| 00240 | | 170 IF (1,1) .OM. MAX |
| 00241 | | 180 IF (1,1) .OM. MAX |
| 00242 | | 190 IF (1,1) .OM. MAX |
| 00243 | | 200 IF (1,1) .OM. MAX |
| 00244 | | 210 IF (1,1) .OM. MAX |
| 00245 | | 220 IF (1,1) .OM. MAX |
| 00246 | | 230 IF (1,1) .OM. MAX |
| 00247 | | 240 IF (1,1) .OM. MAX |
| 00248 | | 250 IF (1,1) .OM. MAX |
| 00249 | | 260 IF (1,1) .OM. MAX |
| 00250 | | 270 IF (1,1) .OM. MAX |
| 00251 | | 280 IF (1,1) .OM. MAX |
| 00252 | | 290 IF (1,1) .OM. MAX |
| 00253 | | 300 IF (1,1) .OM. MAX |
| 00254 | | 310 IF (1,1) .OM. MAX |
| 00255 | | 320 IF (1,1) .OM. MAX |
| 00256 | | 330 IF (1,1) .OM. MAX |
| 00257 | | 340 IF (1,1) .OM. MAX |
| 00258 | | 350 IF (1,1) .OM. MAX |
| 00259 | | 360 IF (1,1) .OM. MAX |
| 00260 | | 370 IF (1,1) .OM. MAX |
| 00261 | | 380 IF (1,1) .OM. MAX |
| 00262 | | 390 IF (1,1) .OM. MAX |
| 00263 | | 400 IF (1,1) .OM. MAX |
| 00264 | | 410 IF (1,1) .OM. MAX |
| 00265 | | 420 IF (1,1) .OM. MAX |
| 00266 | | 430 IF (1,1) .OM. MAX |
| 00267 | | 440 IF (1,1) .OM. MAX |
| 00268 | | 450 IF (1,1) .OM. MAX |
| 00269 | | 460 IF (1,1) .OM. MAX |
| 00270 | | 470 IF (1,1) .OM. MAX |
| 00271 | | 480 IF (1,1) .OM. MAX |
| 00272 | | 490 IF (1,1) .OM. MAX |
| 00273 | | 500 IF (1,1) .OM. MAX |
| 00274 | | 510 IF (1,1) .OM. MAX |
| 00275 | | 520 IF (1,1) .OM. MAX |
| 00276 | | 530 IF (1,1) .OM. MAX |
| 00277 | | 540 IF (1,1) .OM. MAX |
| 00278 | | 550 IF (1,1) .OM. MAX |
| 00279 | | 560 IF (1,1) .OM. MAX |
| 00280 | | 570 IF (1,1) .OM. MAX |
| 00281 | | 580 IF (1,1) .OM. MAX |
| 00282 | | 590 IF (1,1) .OM. MAX |
| 00283 | | 600 IF (1,1) .OM. MAX |
| 00284 | | 610 IF (1,1) .OM. MAX |
| 00285 | | 620 IF (1,1) .OM. MAX |
| 00286 | | 630 IF (1,1) .OM. MAX |
| 00287 | | 640 IF (1,1) .OM. MAX |
| 00288 | | 650 IF (1,1) .OM. MAX |
| 00289 | | 660 IF (1,1) .OM. MAX |
| 00290 | | 670 IF (1,1) .OM. MAX |
| 00291 | | 680 IF (1,1) .OM. MAX |
| 00292 | | 690 IF (1,1) .OM. MAX |
| 00293 | | 700 IF (1,1) .OM. MAX |
| 00294 | | 710 IF (1,1) .OM. MAX |
| 00295 | | 720 IF (1,1) .OM. MAX |
| 00296 | | 730 IF (1,1) .OM. MAX |
| 00297 | | 740 IF (1,1) .OM. MAX |
| 00298 | | 750 IF (1,1) .OM. MAX |
| 00299 | | 760 IF (1,1) .OM. MAX |
| 00300 | | 770 IF (1,1) .OM. MAX |
| 00301 | | 780 IF (1,1) .OM. MAX |
| 00302 | | 790 IF (1,1) .OM. MAX |
| 00303 | | 800 IF (1,1) .OM. MAX |
| 00304 | | 810 IF (1,1) .OM. MAX |
| 00305 | | 820 IF (1,1) .OM. MAX |
| 00306 | | 830 IF (1,1) .OM. MAX |
| 00307 | | 840 IF (1,1) .OM. MAX |
| 00308 | | 850 IF (1,1) .OM. MAX |
| 00309 | | 860 IF (1,1) .OM. MAX |
| 00310 | | 870 IF (1,1) .OM. MAX |
| 00311 | | 880 IF (1,1) .OM. MAX |
| 003 | | |

| | | | |
|-------|------|---|----------|
| 00300 | 1170 | 11 IN-EG-11 60 TO 540 | 00300117 |
| 00301 | 1180 | IF IN-EG-21 60 TO 120 | 00300118 |
| 00302 | 1190 | C D-MATRIX DATA ON TAPE FILE | 00300119 |
| 00303 | 1200 | KEY-2 | 00300120 |
| 00304 | 1210 | C READ U-MATRIX ARRAY FROM TAPE FILE | 00300121 |
| 00305 | 1220 | CALL M-FILMAT,LCOMB,MOFEAT,FETVEC,KEY) | 00300122 |
| 00306 | 1230 | 60 TO 130 | 00300123 |
| 00307 | 1240 | C D-MATRIX DATA READ FROM CARD FILE | 00300124 |
| 00308 | 1250 | 120 KEY-1 M-FILMAT,LCOMB,MOFEAT,FETVEC,KEY) | 00300125 |
| 00309 | 1260 | 130 M-FET2-MOFEAT | 00300126 |
| 00310 | 1270 | DU 140 M-FILMAT | 00300127 |
| 00311 | 1280 | DU 150 M-FILMAT | 00300128 |
| 00312 | 1290 | 140 FETVC2(M-FETVEC(M)) | 00300129 |
| 00313 | 1300 | 60 TO 50 | 00300130 |
| 00314 | 1310 | C FEATURE CARD | 00300131 |
| 00315 | 1320 | 150 CONTINUE | 00300132 |
| 00316 | 1330 | C FURNAT CARD | 00300133 |
| 00317 | 1340 | 160 CONTINUE | 00300134 |
| 00318 | 1350 | 170 M-FINDICAND2,COL,FAVECI1 | 00300135 |
| 00319 | 1360 | | 00300136 |
| 00320 | 1370 | | 00300137 |

| | | | |
|-------|------|---------------------------------|----------|
| 00324 | 1380 | IF IN-EG-11 60 TO 540 | 00300138 |
| 00325 | 1390 | K2-FINDICAND2,COL,SINVEC1 | 00300139 |
| 00326 | 1400 | K3-FINDICAND2,COL,FAVECI1 | 00300140 |
| 00327 | 1410 | IF IN-EG-21 60 TO 120 | 00300141 |
| 00328 | 1420 | IF IN-EG-31 AND (KEY-2) OUTPT-1 | 00300142 |
| 00329 | 1430 | Z-FINDICAND2,COL,SINVEC1 | 00300143 |
| 00330 | 1440 | IF (Z-NE-2) 60 TO 50 | 00300144 |
| 00331 | 1450 | 60 TO 170 | 00300145 |
| 00332 | 1460 | C M-EG CARD (30,220)MEDI | 00300146 |
| 00333 | 1470 | 180 READ 60 TO 50 | 00300147 |
| 00334 | 1480 | C M-EG2 CARD (30,220)MEDI | 00300148 |
| 00335 | 1490 | 190 READ 60 TO 50 | 00300149 |
| 00336 | 1500 | C COMMENT CARD | 00300150 |
| 00337 | 1510 | 200 READ (30,220)COMMENT | 00300151 |
| 00338 | 1520 | 60 TO 50 | 00300152 |
| 00339 | 1530 | C DATE CARD | 00300153 |
| 00340 | 1540 | 210 M-EG2 CARD (30,220)MEDI | 00300154 |
| 00341 | 1550 | IF IN-EG-31 AND (KEY-2) OUTPT-1 | 00300155 |
| 00342 | 1560 | 220 READ (30,220)DATE | 00300156 |
| 00343 | 1570 | 230 FORMATTED (10,10)A61 | 00300157 |
| 00344 | 1580 | 60 TO 50 | 00300158 |
| 00345 | 1590 | C M-EG2 CARD (30,220)MEDI | 00300159 |
| 00346 | 1600 | IF IN-EG-31 AND (KEY-2) OUTPT-1 | 00300160 |
| 00347 | 1610 | 240 READ (30,220)DATE | 00300161 |
| 00348 | 1620 | 250 FORMATTED (10,10)A61 | 00300162 |
| 00349 | 1630 | 60 TO 50 | 00300163 |
| 00350 | 1640 | C M-EG2 CARD (30,220)MEDI | 00300164 |
| 00351 | 1650 | IF IN-EG-31 AND (KEY-2) OUTPT-1 | 00300165 |
| 00352 | 1660 | 260 READ (30,220)DATE | 00300166 |
| 00353 | 1670 | 270 FORMATTED (10,10)A61 | 00300167 |
| 00354 | 1680 | 60 TO 50 | 00300168 |
| 00355 | 1690 | C M-EG2 CARD (30,220)MEDI | 00300169 |
| 00356 | 1700 | IF IN-EG-31 AND (KEY-2) OUTPT-1 | 00300170 |
| 00357 | 1710 | 280 READ (30,220)DATE | 00300171 |
| 00358 | 1720 | 290 FORMATTED (10,10)A61 | 00300172 |
| 00359 | 1730 | 60 TO 50 | 00300173 |
| 00360 | 1740 | C M-EG2 CARD (30,220)MEDI | 00300174 |
| 00361 | 1750 | IF IN-EG-31 AND (KEY-2) OUTPT-1 | 00300175 |
| 00362 | 1760 | 300 READ (30,220)DATE | 00300176 |
| 00363 | 1770 | 310 FORMATTED (10,10)A61 | 00300177 |
| 00364 | 1780 | 60 TO 50 | 00300178 |
| 00365 | 1790 | C M-EG2 CARD (30,220)MEDI | 00300179 |
| 00366 | 1800 | IF IN-EG-31 AND (KEY-2) OUTPT-1 | 00300180 |
| 00367 | 1810 | 320 READ (30,220)DATE | 00300181 |
| 00368 | 1820 | 330 FORMATTED (10,10)A61 | 00300182 |
| 00369 | 1830 | 60 TO 50 | 00300183 |
| 00370 | 1840 | C M-EG2 CARD (30,220)MEDI | 00300184 |
| 00371 | 1850 | IF IN-EG-31 AND (KEY-2) OUTPT-1 | 00300185 |
| 00372 | 1860 | 340 READ (30,220)DATE | 00300186 |
| 00373 | 1870 | 350 FORMATTED (10,10)A61 | 00300187 |
| 00374 | 1880 | 60 TO 50 | 00300188 |
| 00375 | 1890 | C M-EG2 CARD (30,220)MEDI | 00300189 |
| 00376 | 1900 | IF IN-EG-31 AND (KEY-2) OUTPT-1 | 00300190 |
| 00377 | 1910 | 360 READ (30,220)DATE | 00300191 |
| 00378 | 1920 | 370 FORMATTED (10,10)A61 | 00300192 |
| 00379 | 1930 | 60 TO 50 | 00300193 |
| 00380 | 1940 | C M-EG2 CARD (30,220)MEDI | 00300194 |
| 00381 | 1950 | IF IN-EG-31 AND (KEY-2) OUTPT-1 | 00300195 |
| 00382 | 1960 | 380 READ (30,220)DATE | 00300196 |
| 00383 | 1970 | 390 FORMATTED (10,10)A61 | 00300197 |
| 00384 | 1980 | 60 TO 50 | 00300198 |
| 00385 | 1990 | C M-EG2 CARD (30,220)MEDI | 00300199 |
| 00386 | 2000 | IF IN-EG-31 AND (KEY-2) OUTPT-1 | 00300200 |
| 00387 | 2010 | 400 READ (30,220)DATE | 00300201 |
| 00388 | 2020 | 410 FORMATTED (10,10)A61 | 00300202 |
| 00389 | 2030 | 60 TO 50 | 00300203 |
| 00390 | 2040 | C M-EG2 CARD (30,220)MEDI | 00300204 |
| 00391 | 2050 | IF IN-EG-31 AND (KEY-2) OUTPT-1 | 00300205 |
| 00392 | 2060 | 420 READ (30,220)DATE | 00300206 |
| 00393 | 2070 | 430 FORMATTED (10,10)A61 | 00300207 |
| 00394 | 2080 | 60 TO 50 | 00300208 |
| 00395 | 2090 | C M-EG2 CARD (30,220)MEDI | 00300209 |
| 00396 | 2100 | IF IN-EG-31 AND (KEY-2) OUTPT-1 | 00300210 |
| 00397 | 2110 | 440 READ (30,220)DATE | 00300211 |
| 00398 | 2120 | 450 FORMATTED (10,10)A61 | 00300212 |
| 00399 | 2130 | 60 TO 50 | 00300213 |
| 00400 | 2140 | C M-EG2 CARD (30,220)MEDI | 00300214 |
| 00401 | 2150 | IF IN-EG-31 AND (KEY-2) OUTPT-1 | 00300215 |
| 00402 | 2160 | 460 READ (30,220)DATE | 00300216 |
| 00403 | 2170 | 470 FORMATTED (10,10)A61 | 00300217 |
| 00404 | 2180 | 60 TO 50 | 00300218 |
| 00405 | 2190 | C M-EG2 CARD (30,220)MEDI | 00300219 |
| 00406 | 2200 | IF IN-EG-31 AND (KEY-2) OUTPT-1 | 00300220 |
| 00407 | 2210 | 480 READ (30,220)DATE | 00300221 |
| 00408 | 2220 | 490 FORMATTED (10,10)A61 | 00300222 |
| 00409 | 2230 | 60 TO 50 | 00300223 |
| 00410 | 2240 | C M-EG2 CARD (30,220)MEDI | 00300224 |
| 00411 | 2250 | IF IN-EG-31 AND (KEY-2) OUTPT-1 | 00300225 |
| 00412 | 2260 | 500 READ (30,220)DATE | 00300226 |
| 00413 | 2270 | 510 FORMATTED (10,10)A61 | 00300227 |
| 00414 | 2280 | 60 TO 50 | 00300228 |
| 00415 | 2290 | C M-EG2 CARD (30,220)MEDI | 00300229 |

ORIGINAL PAGE IS
OF POOR QUALITY

| | | |
|------|---|-----------|
| 1750 | M = NUMBER 1 (CARD2, COL, ARRAY, 200) | SET100175 |
| 1760 | PEROUT = ARRAY(1) | SET100176 |
| 1770 | IF (M-1) GO TO 90 | SET100177 |
| 1780 | GO TO 50 | SET100178 |
| 1790 | C SUBCLASS CARD | SET100179 |
| 1800 | 270 MDSUB2=NUMBER1(CARD2, COL, SUBVC, MDSUB2) | SET100180 |
| 1810 | CALL ORCH(SUBVC2, MDSUB2) | SET100181 |
| 1820 | GO TO 50 | SET100182 |
| 1830 | C LAN | SET100183 |
| 1840 | 200 J=NUMBER(CARD2, COL) | SET100184 |
| 1850 | IF (J-20) (BLANK) GO TO 540 | SET100185 |
| 1860 | COL=CUL-1 | SET100186 |
| 1870 | M = NUMBER 1 (CARD2, COL, ARRAY, ZERO) | SET100187 |
| 1880 | LAN = ARRAY(1) | SET100188 |
| 1890 | IF (M-1) GO TO 90 | SET100189 |
| 1900 | GO TO 50 | SET100190 |
| 1910 | C | SET100191 |
| 1920 | C | SET100192 |
| 1930 | C | SET100193 |
| 1940 | C | SET100194 |
| 1950 | C | SET100195 |
| 1960 | C | SET100196 |

| | | |
|------|------------------------------|-----------|
| 1970 | C OPTION CARD | SET100197 |
| 1980 | 290 M=INDIC(CARD2, COL, MTR) | SET100198 |
| 1990 | M = 1 AND M 7 | SET100199 |
| 2000 | IF (M-1) (M-6) (5) GO TO 540 | SET100200 |
| 2010 | IF (M-1) (M-6) (5) GO TO 540 | SET100201 |
| 2020 | IF (M-1) (M-6) (5) GO TO 540 | SET100202 |
| 2030 | IF (M-1) (M-6) (5) GO TO 540 | SET100203 |
| 2040 | IF (M-1) (M-6) (5) GO TO 540 | SET100204 |
| 2050 | IF (M-1) (M-6) (5) GO TO 540 | SET100205 |
| 2060 | IF (M-1) (M-6) (5) GO TO 540 | SET100206 |
| 2070 | IF (M-1) (M-6) (5) GO TO 540 | SET100207 |
| 2080 | IF (M-1) (M-6) (5) GO TO 540 | SET100208 |
| 2090 | IF (M-1) (M-6) (5) GO TO 540 | SET100209 |
| 2100 | IF (M-1) (M-6) (5) GO TO 540 | SET100210 |
| 2110 | IF (M-1) (M-6) (5) GO TO 540 | SET100211 |
| 2120 | IF (M-1) (M-6) (5) GO TO 540 | SET100212 |
| 2130 | IF (M-1) (M-6) (5) GO TO 540 | SET100213 |
| 2140 | IF (M-1) (M-6) (5) GO TO 540 | SET100214 |
| 2150 | IF (M-1) (M-6) (5) GO TO 540 | SET100215 |
| 2160 | IF (M-1) (M-6) (5) GO TO 540 | SET100216 |
| 2170 | IF (M-1) (M-6) (5) GO TO 540 | SET100217 |
| 2180 | IF (M-1) (M-6) (5) GO TO 540 | SET100218 |
| 2190 | IF (M-1) (M-6) (5) GO TO 540 | SET100219 |
| 2200 | IF (M-1) (M-6) (5) GO TO 540 | SET100220 |
| 2210 | IF (M-1) (M-6) (5) GO TO 540 | SET100221 |
| 2220 | IF (M-1) (M-6) (5) GO TO 540 | SET100222 |
| 2230 | IF (M-1) (M-6) (5) GO TO 540 | SET100223 |
| 2240 | IF (M-1) (M-6) (5) GO TO 540 | SET100224 |
| 2250 | IF (M-1) (M-6) (5) GO TO 540 | SET100225 |
| 2260 | IF (M-1) (M-6) (5) GO TO 540 | SET100226 |
| 2270 | IF (M-1) (M-6) (5) GO TO 540 | SET100227 |
| 2280 | IF (M-1) (M-6) (5) GO TO 540 | SET100228 |
| 2290 | IF (M-1) (M-6) (5) GO TO 540 | SET100229 |
| 2300 | IF (M-1) (M-6) (5) GO TO 540 | SET100230 |
| 2310 | IF (M-1) (M-6) (5) GO TO 540 | SET100231 |
| 2320 | IF (M-1) (M-6) (5) GO TO 540 | SET100232 |

| | | | |
|--------|------|--|------------|
| 000000 | 2300 | IF M = 9, 0 50 --- CHECK FOR 'SCAFAC'. | 2100000000 |
| 000000 | 2310 | 320 J = MATCH (CARD2, COL) | 2100000000 |
| 000000 | 2320 | IF NEXT CHARACTER IS 'C', ASSURE 'SCAFAC'. | 2100000000 |
| 000000 | 2330 | IF (J-NE-C) GO TO 540 | 2100000000 |
| 000000 | 2340 | Z = FIND (CARD2, COL, SINVEC) | 2100000000 |
| 000000 | 2350 | IF (Z-EQ-3) GO TO 330 | 2100000000 |
| 000000 | 2360 | GO TO 540 | 2100000000 |
| 000000 | 2370 | SCALE FACTOR OPTION: READ SCALING PAIRS, COM AND MIN, INTO | 2100000000 |
| 000000 | 2380 | COMIN | 2100000000 |
| 000000 | 2390 | | 2100000000 |
| 000000 | 2400 | | 2100000000 |
| 000000 | 2410 | | 2100000000 |
| 000000 | 2420 | | 2100000000 |
| 000000 | 2430 | | 2100000000 |
| 000000 | 2440 | | 2100000000 |
| 000000 | 2450 | | 2100000000 |
| 000000 | 2460 | | 2100000000 |
| 000000 | 2470 | | 2100000000 |
| 000000 | 2480 | | 2100000000 |
| 000000 | 2490 | | 2100000000 |
| 000000 | 2500 | | 2100000000 |
| 000000 | 2510 | | 2100000000 |
| 000000 | 2520 | | 2100000000 |
| 000000 | 2530 | | 2100000000 |
| 000000 | 2540 | | 2100000000 |

| | | | |
|--------|------|---|------------|
| 000000 | 2550 | 330 SCAFLC = 3 | 2100000000 |
| 000000 | 2560 | 340 Z = FIND (CARD2, COL, OP) | 2100000000 |
| 000000 | 2570 | IF (Z-NE-2) GO TO 50 | 2100000000 |
| 000000 | 2580 | NNN = PLTNUM (CARD2, COL, COMMINSF) * 2 | 2100000000 |
| 000000 | 2590 | IF (NNN-NE-2) GO TO 540 | 2100000000 |
| 000000 | 2600 | ADDNMM = NSF * (1-31) GO TO 50 | 2100000000 |
| 000000 | 2610 | IF (NSF-NNN) GO TO 50 | 2100000000 |
| 000000 | 2620 | NSF = NSF * NNN | 2100000000 |
| 000000 | 2630 | Z = FIND (CARD2, COL, CP) | 2100000000 |
| 000000 | 2640 | IF (Z-EQ-2) GO TO 340 | 2100000000 |
| 000000 | 2650 | GO TO 540 | 2100000000 |
| 000000 | 2660 | PUNCH OPTION | 2100000000 |
| 000000 | 2670 | 350 MPUN = 1 | 2100000000 |
| 000000 | 2680 | GO TO 290 | 2100000000 |
| 000000 | 2690 | MODULE STAT DICK | 2100000000 |
| 000000 | 2700 | 360 M-MATCH (CARD2, COL) | 2100000000 |
| 000000 | 2710 | IF (M-NE-TEST(3)) GO TO 370 | 2100000000 |
| 000000 | 2720 | SCAFLC = 2 | 2100000000 |
| 000000 | 2730 | | 2100000000 |
| 000000 | 2740 | | 2100000000 |
| 000000 | 2750 | | 2100000000 |
| 000000 | 2760 | | 2100000000 |
| 000000 | 2770 | | 2100000000 |
| 000000 | 2780 | | 2100000000 |
| 000000 | 2790 | | 2100000000 |
| 000000 | 2800 | | 2100000000 |
| 000000 | 2810 | | 2100000000 |
| 000000 | 2820 | | 2100000000 |
| 000000 | 2830 | | 2100000000 |
| 000000 | 2840 | | 2100000000 |
| 000000 | 2850 | | 2100000000 |
| 000000 | 2860 | | 2100000000 |
| 000000 | 2870 | | 2100000000 |
| 000000 | 2880 | | 2100000000 |
| 000000 | 2890 | | 2100000000 |
| 000000 | 2900 | | 2100000000 |
| 000000 | 2910 | | 2100000000 |
| 000000 | 2920 | | 2100000000 |
| 000000 | 2930 | | 2100000000 |
| 000000 | 2940 | | 2100000000 |
| 000000 | 2950 | | 2100000000 |
| 000000 | 2960 | | 2100000000 |
| 000000 | 2970 | | 2100000000 |
| 000000 | 2980 | | 2100000000 |
| 000000 | 2990 | | 2100000000 |
| 000000 | 3000 | | 2100000000 |


```

00637 4090 C
00638 4091 C
00639 4092 C
00640 4093 C
00641 4094 C
00642 4095 C
00643 4096 C
00644 4097 C
00645 4098 C
00646 4099 C
00647 4100 C
00648 4101 C
00649 4102 C
00650 4103 C
00651 4104 C
00652 4105 C
00653 4106 C
00654 4107 C
00655 4108 C
00656 4109 C
00657 4110 C

```

DO 510 101.10
 TEMP COMENT(1)
 COMENT(1) = COVNDIT1
 510 COVNDIT1 = TEMP
 C
 CALL PATCOV(ARRAY(COVAR2), VARS2, NOFET2, ARRAY(SUBS2))
 C
 DO 520 101.10
 TEMP COMENT(1) = COVNDIT1
 520 COVNDIT1 = TEMP
 C
 PRINT OUT THE INPUT TRANSFORMATION MATRIX
 C
 530 CALL MATRIN(MAT, NOFET4, NOFET2, FETVC2)
 SET NOCLS2=NOFET2 FOR NEXT OF PROGRAM
 C
 NOCLS2=NOFET2
 C

```

00657 4290 C
00658 4291 C
00659 4292 C
00660 4293 C
00661 4294 C
00662 4295 C
00663 4296 C
00664 4297 C
00665 4298 C
00666 4299 C
00667 4300 C
00668 4301 C
00669 4302 C
00670 4303 C
00671 4304 C
00672 4305 C
00673 4306 C
00674 4307 C
00675 4308 C
00676 4309 C
00677 4310 C
00678 4311 C
00679 4312 C
00680 4313 C
00681 4314 C
00682 4315 C
00683 4316 C
00684 4317 C
00685 4318 C
00686 4319 C
00687 4320 C
00688 4321 C
00689 4322 C
00690 4323 C
00691 4324 C
00692 4325 C
00693 4326 C
00694 4327 C
00695 4328 C
00696 4329 C
00697 4330 C
00698 4331 C
00699 4332 C
00700 4333 C
00701 4334 C
00702 4335 C
00703 4336 C
00704 4337 C
00705 4338 C
00706 4339 C
00707 4340 C
00708 4341 C
00709 4342 C
00710 4343 C
00711 4344 C
00712 4345 C
00713 4346 C
00714 4347 C
00715 4348 C
00716 4349 C
00717 4350 C
00718 4351 C
00719 4352 C
00720 4353 C
00721 4354 C
00722 4355 C
00723 4356 C
00724 4357 C
00725 4358 C
00726 4359 C
00727 4360 C
00728 4361 C
00729 4362 C
00730 4363 C
00731 4364 C
00732 4365 C
00733 4366 C
00734 4367 C
00735 4368 C
00736 4369 C
00737 4370 C
00738 4371 C
00739 4372 C
00740 4373 C
00741 4374 C
00742 4375 C
00743 4376 C
00744 4377 C
00745 4378 C
00746 4379 C
00747 4380 C
00748 4381 C
00749 4382 C
00750 4383 C
00751 4384 C
00752 4385 C
00753 4386 C
00754 4387 C
00755 4388 C
00756 4389 C
00757 4390 C
00758 4391 C
00759 4392 C
00760 4393 C
00761 4394 C
00762 4395 C
00763 4396 C
00764 4397 C
00765 4398 C
00766 4399 C
00767 4400 C
00768 4401 C
00769 4402 C
00770 4403 C
00771 4404 C
00772 4405 C
00773 4406 C
00774 4407 C
00775 4408 C
00776 4409 C
00777 4410 C
00778 4411 C
00779 4412 C
00780 4413 C
00781 4414 C
00782 4415 C
00783 4416 C
00784 4417 C
00785 4418 C
00786 4419 C
00787 4420 C
00788 4421 C
00789 4422 C
00790 4423 C
00791 4424 C
00792 4425 C
00793 4426 C
00794 4427 C
00795 4428 C
00796 4429 C
00797 4430 C
00798 4431 C
00799 4432 C
00800 4433 C
00801 4434 C
00802 4435 C
00803 4436 C
00804 4437 C
00805 4438 C
00806 4439 C
00807 4440 C
00808 4441 C
00809 4442 C
00810 4443 C
00811 4444 C
00812 4445 C
00813 4446 C
00814 4447 C
00815 4448 C
00816 4449 C
00817 4450 C
00818 4451 C
00819 4452 C
00820 4453 C
00821 4454 C
00822 4455 C
00823 4456 C
00824 4457 C
00825 4458 C
00826 4459 C
00827 4460 C
00828 4461 C
00829 4462 C
00830 4463 C
00831 4464 C
00832 4465 C
00833 4466 C
00834 4467 C
00835 4468 C
00836 4469 C
00837 4470 C
00838 4471 C
00839 4472 C
00840 4473 C
00841 4474 C
00842 4475 C
00843 4476 C
00844 4477 C
00845 4478 C
00846 4479 C
00847 4480 C
00848 4481 C
00849 4482 C
00850 4483 C
00851 4484 C
00852 4485 C
00853 4486 C
00854 4487 C
00855 4488 C
00856 4489 C
00857 4490 C
00858 4491 C
00859 4492 C
00860 4493 C
00861 4494 C
00862 4495 C
00863 4496 C
00864 4497 C
00865 4498 C
00866 4499 C
00867 4500 C
00868 4501 C
00869 4502 C
00870 4503 C
00871 4504 C
00872 4505 C
00873 4506 C
00874 4507 C
00875 4508 C
00876 4509 C
00877 4510 C
00878 4511 C
00879 4512 C
00880 4513 C
00881 4514 C
00882 4515 C
00883 4516 C
00884 4517 C
00885 4518 C
00886 4519 C
00887 4520 C
00888 4521 C
00889 4522 C
00890 4523 C
00891 4524 C
00892 4525 C
00893 4526 C
00894 4527 C
00895 4528 C
00896 4529 C
00897 4530 C
00898 4531 C
00899 4532 C
00900 4533 C
00901 4534 C
00902 4535 C
00903 4536 C
00904 4537 C
00905 4538 C
00906 4539 C
00907 4540 C
00908 4541 C
00909 4542 C
00910 4543 C
00911 4544 C
00912 4545 C
00913 4546 C
00914 4547 C
00915 4548 C
00916 4549 C
00917 4550 C
00918 4551 C
00919 4552 C
00920 4553 C
00921 4554 C
00922 4555 C
00923 4556 C
00924 4557 C
00925 4558 C
00926 4559 C
00927 4560 C
00928 4561 C
00929 4562 C
00930 4563 C
00931 4564 C
00932 4565 C
00933 4566 C
00934 4567 C
00935 4568 C
00936 4569 C
00937 4570 C
00938 4571 C
00939 4572 C
00940 4573 C
00941 4574 C
00942 4575 C
00943 4576 C
00944 4577 C
00945 4578 C
00946 4579 C
00947 4580 C
00948 4581 C
00949 4582 C
00950 4583 C
00951 4584 C
00952 4585 C
00953 4586 C
00954 4587 C
00955 4588 C
00956 4589 C
00957 4590 C
00958 4591 C
00959 4592 C
00960 4593 C
00961 4594 C
00962 4595 C
00963 4596 C
00964 4597 C
00965 4598 C
00966 4599 C
00967 4600 C
00968 4601 C
00969 4602 C
00970 4603 C
00971 4604 C
00972 4605 C
00973 4606 C
00974 4607 C
00975 4608 C
00976 4609 C
00977 4610 C
00978 4611 C
00979 4612 C
00980 4613 C
00981 4614 C
00982 4615 C
00983 4616 C
00984 4617 C
00985 4618 C
00986 4619 C
00987 4620 C
00988 4621 C
00989 4622 C
00990 4623 C
00991 4624 C
00992 4625 C
00993 4626 C
00994 4627 C
00995 4628 C
00996 4629 C
00997 4630 C
00998 4631 C
00999 4632 C

```

ORIGINAL PAGE
OF POOR QUALITY

END OF COMPILATION: NO DIAGNOSTICS.

SETUP8 CODE RELOCATABLE
 25 APR 77 10125:10 0 02710154 14 449 10ELETED
 25 APR 77 10125:10 0 02724264 90 109 10ELETED
 0 02724344 14 109

[illegible]

```

000101 10 SUBROUTINE KBTAN
000102 20 I BNAT, LCOMB, ANRAY, LAN, MAX, MIN, EPS, TRANSF)
000103 30 C
000104 40 C IMPLICIT INTEGER(A-Z)
000105 50 C
000106 60 C DIMENSION COVMD2(16)
000107 70 C
000108 80 C DIMENSION ARRAY(1)
000109 90 REAL TMIN, TMAX
000110
000111
000112
000113
000114
000115
000116
000117
000118
000119
000120
000121
000122
000123
000124
000125
000126
000127
000128
000129
000130
000131
000132
000133
000134
000135
000136
000137
000138
000139
000140
000141
000142
000143
000144
000145
000146
000147
000148
000149
000150
000151
000152
000153
000154
000155
000156
000157
000158
000159
000160
000161
000162
000163
000164
000165
000166
000167
000168
000169
000170
000171
000172
000173
000174
000175
000176
000177
000178
000179
000180
000181
000182
000183
000184
000185
000186
000187
000188
000189
000190
000191
000192
000193
000194
000195
000196
000197
000198
000199
000200
000201
000202
000203
000204
000205
000206
000207
000208
000209
000210
000211
000212
000213
000214
000215
000216
000217
000218
000219
000220
000221
000222
000223
000224
000225
000226
000227
000228
000229
000230
000231
000232
000233
000234
000235
000236
000237
000238
000239
000240
000241
000242
000243
000244
000245
000246
000247
000248
000249
000250
000251
000252
000253
000254
000255
000256
000257
000258
000259
000260
000261
000262
000263
000264
000265
000266
000267
000268
000269
000270
000271
000272
000273
000274
000275
000276
000277
000278
000279
000280
000281
000282
000283
000284
000285
000286
000287
000288
000289
000290
000291
000292
000293
000294
000295
000296
000297
000298
000299
000300
000301
000302
000303
000304
000305
000306
000307
000308
000309
000310
000311
000312
000313
000314
000315
000316
000317
000318
000319
000320
000321
000322
000323
000324
000325
000326
000327
000328
000329
000330
000331
000332
000333
000334
000335
000336
000337
000338
000339
000340
000341
000342
000343
000344
000345
000346
000347
000348
000349
000350
000351
000352
000353
000354
000355
000356
000357
000358
000359
000360
000361
000362
000363
000364
000365
000366
000367
000368
000369
000370
000371
000372
000373
000374
000375
000376
000377
000378
000379
000380
000381
000382
000383
000384
000385
000386
000387
000388
000389
000390
000391
000392
000393
000394
000395
000396
000397
000398
000399
000400
000401
000402
000403
000404
000405
000406
000407
000408
000409
000410
000411
000412
000413
000414
000415
000416
000417
000418
000419
000420
000421
000422
000423
000424
000425
000426
000427
000428
000429
000430
000431
000432
000433
000434
000435
000436
000437
000438
000439
000440
000441
000442
000443
000444
000445
000446
000447
000448
000449
000450
000451
000452
000453
000454
000455
000456
000457
000458
000459
000460
000461
000462
000463
000464
000465
000466
000467
000468
000469
000470
000471
000472
000473
000474
000475
000476
000477
000478
000479
000480
000481
000482
000483
000484
000485
000486
000487
000488
000489
000490
000491
000492
000493
000494
000495
000496
000497
000498
000499
000500
000501
000502
000503
000504
000505
000506
000507
000508
000509
000510
000511
000512
000513
000514
000515
000516
000517
000518
000519
000520
000521
000522
000523
000524
000525
000526
000527
000528
000529
000530
000531
000532
000533
000534
000535
000536
000537
000538
000539
000540
000541
000542
000543
000544
000545
000546
000547
000548
000549
000550
000551
000552
000553
000554
000555
000556
000557
000558
000559
000560
000561
000562
000563
000564
000565
000566
000567
000568
000569
000570
000571
000572
000573
000574
000575
000576
000577
000578
000579
000580
000581
000582
000583
000584
000585
000586
000587
000588
000589
000590
000591
000592
000593
000594
000595
000596
000597
000598
000599
000600
000601
000602
000603
000604
000605
000606
000607
000608
000609
000610
000611
000612
000613
000614
000615
000616
000617
000618
000619
000620
000621
000622
000623
000624
000625
000626
000627
000628
000629
000630
000631
000632
000633
000634
000635
000636
000637
000638
000639
000640
000641
000642
000643
000644
000645
000646
000647
000648
000649
000650
000651
000652
000653
000654
000655
000656
000657
000658
000659
000660
000661
000662
000663
000664
000665
000666
000667
000668
000669
000670
000671
000672

```

| | | | | |
|-------|---|---|--|----------|
| 00106 | C | REAL | BHAT(400), MAX(16), MIN(16), EPS(16) | KBTN0003 |
| 00107 | C | REAL | SC(400), SC(400), D(16), DIAG(400), BMEAN(900) | KBTN0001 |
| 00110 | C | INCLUDE COMBK1.LIST | | KBTN0012 |
| 00110 | C | COMMON/INFOM/NOCLS2,NOSUB2,NOFET2,VARSZ2,TOIV12,NOFL2, | | KBTN0013 |
| 00111 | C | COMMON/INFOM/NOCLS2,NOSUB2,NOFET2,VARSZ2,TOIV12,NOFL2, | | KBTN0015 |
| 00112 | C | AVANZ,COVANZ,CLS102,SUBNU2,SUBNU22,FLUSZ2,RYAZ, | | KBTN0016 |
| 00112 | C | FETVC2(30),SUBVC2(75),SUBPM(75),CLSVZ2(60), | | KBTN0017 |
| 00112 | C | KEPPTS(60),NUGRP,GMPNAM(60),GRPDLA(61), | | KBTN0018 |
| 00112 | C | GRPCNA(61),GMOUP2(124) | | KBTN0020 |
| 00113 | C | END | | KBTN0021 |
| 00113 | C | INCLUDE COMBK9.LIST | | KBTN0022 |
| 00114 | C | TRANSFORMATION COMMON BLUCK | | KBTN0023 |
| 00114 | C | COMMON/MLCK/OUT,MT,NOFEAT,FLDINF(6), ,FETVC(30) | | KBTN0024 |
| 00115 | C | END | | KBTN0025 |
| 00116 | C | INCLUDE COMBK9.LIST | | KBTN0026 |
| 00117 | C | DIMENSION MED(10),HEAD(10),DATE(2),COMENT(10) | | KBTN0027 |
| 00120 | C | EQUIVALENC (MED(10),HEAD(10),DATE(1),HEAD(15)) | | KBTN0028 |
| 00121 | C | END | | KBTN0029 |
| 00121 | C | INCLUDE COMBK6.LIST | | KBTN0030 |
| 00122 | C | COMMON/GLOBAL/HEAD(42),MPTAP,DATE, ,SAVTAP,GMFILE,ONLY, | | KBTN0031 |
| 00123 | C | COMMON/GLOBAL/HEAD(42),MPTAP,DATE, ,SAVTAP,GMFILE,ONLY, | | KBTN0032 |
| 00123 | C | DRUNAUT,DRMADS,PAGSIZ,DATAFIL,STAFIL,ASAV,ASAVFL | | KBTN0033 |
| 00124 | C | END | | KBTN0034 |
| 00124 | C | DIMENSION NSUB(75) | | KBTN0035 |
| 00125 | C | COVHD2(1) = 6M... TR | | KBTN0036 |
| 00126 | C | COVHD2(1) = 6MANSFOR | | KBTN0037 |
| 00127 | C | COVHD2(1) = 6MHEU ST | | KBTN0038 |
| 00130 | C | | | KBTN0039 |
| 00131 | C | | | KBTN0040 |


```

00244 070      THIN = MIN(1)
00245 080      100 CONTINUE
00246 090      IF (MIN(1) .LE. THIN) THIN = MIN(1)
00247 100      110 CONTINUE
00248 110      MIN(1) = THIN
00249 120      MAX(1) = IMAX
00250 130      EPS(1) = 255. / (MAX(1) - MIN(1))
00251 140      120 CONTINUE
00252 150      RETURN
00253 160      END
00254 170
00255 180
00256 190
00257 200
00258 210
00259 220
00260 230
00261 240
00262 250
00263 260
00264 270
00265 280
00266 290
00267 300
00268 310
00269 320
00270 330
00271 340
00272 350
00273 360
00274 370
00275 380
00276 390
00277 400
00278 410
00279 420
00280 430
00281 440
00282 450
00283 460
00284 470
00285 480
00286 490
00287 500
00288 510
00289 520
00290 530
00291 540
00292 550
00293 560
00294 570
00295 580
00296 590
00297 600
00298 610
00299 620
00300 630
00301 640
00302 650
00303 660
00304 670
00305 680
00306 690
00307 700
00308 710
00309 720
00310 730
00311 740
00312 750
00313 760
00314 770
00315 780
00316 790
00317 800
00318 810
00319 820
00320 830
00321 840
00322 850
00323 860
00324 870
00325 880
00326 890
00327 900
00328 910
00329 920
00330 930
00331 940
00332 950
00333 960
00334 970
00335 980
00336 990

```

```

END OF COMPILATION: NO DIAGNOSTICS.
25 APR 77 10:25:13 0 027J0210 19 95 (DELETED)
25 APR 77 10:25:13 0 027J0210 19 95 (DELETED)

```

```

FOR MAXIMUM MAXIMUM
UNIQUE 1106 FORTHAN V EXEC 11 LEVEL 25A - (EXECB LEVEL E12010010A)
THIS COMPILATION WAS DONE ON 09 MAY 77 AT 22:09:14
09 MAY 77 22:09:14

```

```

SUBROUTINE MAXMAT ENTRY POINT 000120

```

```

STORAGE USED: CODE(1) 0001461 DATA(1) 0000351 BLANK COMMON(2) 0000000

```

```

COMMON BLOCKS:
0003 TRUCK 000046

```

```

EXTERNAL REFERENCES (BLOCK, NAME)

```

```

0004 MEMK35

```

```

STORAGE ASSIGNMENT (BLOCK, TYPE, RELATIVE LOCATION, NAME)

```

```

0001 000054 IOL 0001 20023 1126 0001 000031 1176 0001 000044 20L 0003 000019 7E1VEC
0002 000002 FLOINF 0000 1 000000 1 0000 000005 INJPS 0000 1 000001 0 0000 1 000002 0
0003 1 000001 NUFLEAT 0003 000300 OUTFTM

```

```

00101 10 SUBROUTINE MAXMAT ( MAX, MIN, CON, BMAT, LCONB, MAXPT )
00102 20 C COMPUTE AN APPROXIMATE TRANSFORMED MAX AND MIN FOR EACH COMPONENT
00103 30 C OF THE TRANSFORMATION
00104 40 C
00105 50 C IMPLICIT INTEGER(A-Z)
00106 60 C DIMENSION MAXPT(3)
00107 70
00108 80
00109 90
00110 100
00111 110
00112 120
00113 130
00114 140
00115 150
00116 160
00117 170
00118 180
00119 190
00120 200
00121 210
00122 220
00123 230
00124 240
00125 250
00126 260
00127 270
00128 280
00129 290
00130 300
00131 310
00132 320
00133 330
00134 340
00135 350
00136 360
00137 370
00138 380
00139 390
00140 400
00141 410
00142 420
00143 430
00144 440
00145 450
00146 460
00147 470
00148 480
00149 490
00150 500
00151 510
00152 520
00153 530
00154 540
00155 550
00156 560
00157 570
00158 580
00159 590
00160 600
00161 610
00162 620
00163 630
00164 640
00165 650
00166 660
00167 670
00168 680
00169 690
00170 700
00171 710
00172 720
00173 730
00174 740
00175 750
00176 760
00177 770
00178 780
00179 790
00180 800
00181 810
00182 820
00183 830
00184 840
00185 850
00186 860
00187 870
00188 880
00189 890
00190 900
00191 910
00192 920
00193 930
00194 940
00195 950
00196 960
00197 970
00198 980
00199 990

```



```

00104      C      REAL  BMAT(ND), MAX(16), MIN(16), COM(16)
00105      C
00106      C
00107      C      USING INPUT 1 OR DEFAULT 1, MAXIMUM DATA VALUE FOR EACH
00108      C      CHANNEL, COMPUTE THE TRANSFORMED VALUE RANGE, 1 MAX AND MIN 1
00109      C      AND COMPUTE THE HISTOGRAM SCALING FACTOR, 50N,
00110      C
00111      C      INCLUDE COMBET.LIST
00112      C      DATA TRANSFORMATION COMMON BLOCK
00113      C      COMMON/TMPLCS/OUTFMT,NOFEAT,FLDINF(16),
00114      C      FETVECT(30)
00115      C
00116      C      DO 30 I=1,LCOMR
00117      C      MAX(I) = 0.0
00118      C      MIN(I) = 0.0
00119      C      DO 20 J=1,NOFEAT
00120      C      K=J-1+LCOMR+1
00121      C      IF (BMAT(K).LE.0.0) GO TO 10
00122      C
00123      C      MAX(I) = MAX(I) + BMAT(K) * MAXPT(I)
00124      C

```

NAMEU006
 NAMEU007
 NAMEU008
 NAMEU009
 NAMEU010
 NAMEU011
 NAMEU012
 NAMEU013
 NAMEU014
 NAMEU015
 NAMEU016
 NAMEU017
 NAMEU018
 NAMEU019
 NAMEU020
 NAMEU021
 NAMEU022
 NAMEU023

```

00124      C      GO TO 20
00125      C      10 CONTINUE
00126      C
00127      C      MIN(I) = MIN(I) + BMAT(K) * MAXPT(I)
00128      C
00129      C      20 CONTINUE
00130      C      COM(I) = (MAX(I)-MIN(I))/100.
00131      C      30 CONTINUE
00132      C      RETURN
00133      C      END
00134

```

NAMEU024
 NAMEU025
 NAMEU026
 NAMEU027
 NAMEU028
 NAMEU029
 NAMEU030
 NAMEU031
 NAMEU032
 NAMEU033
 NAMEU034

END OF COMPILE: NO DIAGNOSTICS.
 NAMEAT CODE SYMOLIC
 NAMEAT CODE RELUCABLE
 25 APR 77 10125:14 0 04733036 19 39 (DELETED)
 25 APR 77 10125:14 0 04734572 24 31 (DELETED)
 0 04734622 19 31

0 FOR TRMIST TRMIST 09 MAY 77 227 98
 UNIVOL 1100 FORTMAN V EXEC 11 LEVEL 25A -16RECO LEVEL E12010010A1
 THIS COMPILATION WAS DONE ON 09 MAY 77 AT 22109147

SUBROUTINE TRMIST ENTRY POINT 000690

STORAGE USED: CODE(1) 0007501 DATA(0) 0001761 BLANK COMMON(2) 000000

COMMON BLOCKS:

0003 INFORM 001154
 0004 INOLCK 000096
 0005 GLOBAL 100075

EXTERNAL REFERENCES (BLOCK, NAME)

0006 LAHEAD
 0007 TAPHUN
 0008 FLOINT
 0009 LINEAD
 0010 FOLINT
 0011 TRANS
 0012 SORT
 0013 RENH35

STORAGE ASSIGNMENT (BLOCK, TYPE, RELATIVE LOCATION, NAME)

| | | | | | | | | | | | | | | |
|------|--------|------|------|--------|------|------|--------|------|------|--------|------|------|--------|------|
| 0001 | 000003 | 182L | 0001 | 000735 | 110L | 0001 | 000737 | 120L | 0001 | 000055 | 134L | 0001 | 000491 | 140L |
| 0001 | 000513 | 182L | 0001 | 000174 | 110L | 0001 | 000176 | 165L | 0001 | 000536 | 170L | 0001 | 000207 | 175L |
| 0001 | 000513 | 182L | 0001 | 000576 | 170L | 0001 | 000295 | 210L | 0001 | 000510 | 219L | 0001 | 000241 | 217L |
| 0001 | 000311 | 224L | 0001 | 000453 | 265L | 0001 | 000774 | 272L | 0001 | 000510 | 279L | 0001 | 000541 | 312L |
| 0001 | 000322 | 20L | 0001 | 000230 | 50L | 0001 | 000701 | 60L | 0001 | 000405 | 70L | 0001 | 000414 | 80L |

[illegible]

00101 SUBROUTINE TRNISTCTDATA, MAXT, AMIN, ACON, MAT, LCONB,
00102 *PEROUT, FILMS, TOP, LAR, FLOWAN, NC, VENTCS, NAA, MIN, CON,
00103
00104
00105
00106
00107
00108
00109
00110
00111
00112
00113
00114
00115
00116
00117
00118
00119
00120
00121
00122
00123
00124
00125
00126
00127
00128
00129
00130
00131
00132
00133
00134
00135
00136
00137
00138
00139
00140
00141
00142
00143
00144
00145
00146
00147
00148
00149
00150
00151
00152
00153
00154
00155
00156
00157
00158
00159
00160
00161
00162
00163
00164
00165
00166
00167
00168
00169
00170
00171
00172
00173
00174
00175
00176
00177
00178
00179
00180
00181
00182
00183
00184
00185
00186
00187
00188
00189
00190
00191
00192
00193
00194
00195
00196
00197
00198
00199
00200
00201
00202
00203
00204
00205
00206
00207
00208
00209
00210
00211
00212
00213
00214
00215
00216
00217
00218
00219
00220
00221
00222
00223
00224
00225
00226
00227
00228
00229
00230
00231
00232
00233
00234
00235
00236
00237
00238
00239
00240
00241
00242
00243
00244
00245
00246
00247
00248
00249
00250
00251
00252
00253
00254
00255
00256
00257
00258
00259
00260
00261
00262
00263
00264
00265
00266
00267
00268
00269
00270
00271
00272
00273
00274
00275
00276
00277
00278
00279
00280
00281
00282
00283
00284
00285
00286
00287
00288
00289
00290
00291
00292
00293
00294
00295
00296
00297
00298
00299
00300
00301
00302
00303
00304
00305
00306
00307
00308
00309
00310
00311
00312
00313
00314
00315
00316
00317
00318
00319
00320
00321
00322
00323
00324
00325
00326
00327
00328
00329
00330
00331
00332
00333
00334
00335
00336
00337
00338
00339
00340
00341
00342
00343
00344
00345
00346
00347
00348
00349
00350
00351
00352
00353
00354
00355
00356
00357
00358
00359
00360
00361
00362
00363
00364
00365
00366
00367
00368
00369
00370
00371
00372
00373
00374
00375
00376
00377
00378
00379
00380
00381
00382
00383
00384
00385
00386
00387
00388
00389
00390
00391
00392
00393
00394
00395
00396
00397
00398
00399
00400
00401
00402
00403
00404
00405
00406
00407
00408
00409
00410
00411
00412
00413
00414
00415
00416
00417
00418
00419
00420
00421
00422
00423
00424
00425
00426
00427
00428
00429
00430
00431
00432
00433
00434
00435
00436
00437
00438
00439
00440
00441
00442
00443
00444
00445
00446
00447
00448
00449
00450
00451
00452
00453
00454
00455
00456
00457
00458
00459
00460
00461
00462
00463
00464
00465
00466
00467
00468
00469
00470
00471
00472
00473
00474
00475
00476
00477
00478
00479
00480
00481
00482
00483
00484
00485
00486
00487
00488
00489
00490
00491
00492
00493
00494
00495
00496
00497
00498
00499
00500
00501
00502
00503
00504
00505
00506
00507
00508
00509
00510
00511
00512
00513
00514
00515
00516
00517
00518
00519
00520
00521
00522
00523
00524
00525
00526
00527
00528
00529
00530
00531
00532
00533
00534
00535
00536
00537
00538
00539
00540
00541
00542
00543
00544
00545
00546
00547
00548
00549
00550
00551
00552
00553
00554
00555
00556
00557
00558
00559
00560
00561
00562
00563
00564
00565
00566
00567
00568
00569
00570
00571
00572
00573
00574
00575
00576
00577
00578
00579
00580
00581
00582
00583
00584
00585
00586
00587
00588
00589
00590
00591
00592
00593
00594
00595
00596
00597
00598
00599
00600
00601
00602
00603
00604
00605
00606
00607
00608
00609
00610
00611
00612
00613
00614
00615
00616
00617
00618
00619
00620
00621
00622
00623
00624
00625
00626
00627
00628
00629
00630
00631
00632
00633
00634
00635
00636
00637
00638
00639
00640
00641
00642
00643
00644
00645
00646
00647
00648
00649
00650
00651
00652
00653
00654
00655
00656
00657
00658
00659
00660
00661
00662
00663
00664
00665
00666
00667
00668
00669
00670
00671
00672
00673
00674
00675
00676
00677
00

| 000101 | 000102 | 000103 | 000104 | 000105 | 000106 | 000107 | 000108 | 000109 | 000110 | 000111 | 000112 | 000113 | 000114 | 000115 | 000116 | 000117 | 000118 | 000119 | 000120 | 000121 | 000122 | 000123 | 000124 | 000125 | 000126 | 000127 | 000128 | 000129 | 000130 | 000131 | 000132 | 000133 | 000134 | 000135 | 000136 | 000137 | 000138 | 000139 | 000140 | 000141 | 000142 | 000143 | 000144 | 000145 | 000146 | 000147 | 000148 | 000149 | 000150 | 000151 | 000152 | 000153 | 000154 | 000155 | 000156 | 000157 | 000158 | 000159 | 000160 | 000161 | 000162 | 000163 | 000164 | 000165 | 000166 | 000167 | 000168 | 000169 | 000170 | 000171 | 000172 | 000173 | 000174 | 000175 | 000176 | 000177 | 000178 | 000179 | 000180 | 000181 | 000182 | 000183 | 000184 | 000185 | 000186 | 000187 | 000188 | 000189 | 000190 | 000191 | 000192 | 000193 | 000194 | 000195 | 000196 | 000197 | 000198 | 000199 | 000200 | 000201 | 000202 | 000203 | 000204 | 000205 | 000206 | 000207 | 000208 | 000209 | 000210 | 000211 | 000212 | 000213 | 000214 | 000215 | 000216 | 000217 | 000218 | 000219 | 000220 | 000221 | 000222 | 000223 | 000224 | 000225 | 000226 | 000227 | 000228 | 000229 | 000230 | 000231 | 000232 | 000233 | 000234 | 000235 | 000236 | 000237 | 000238 | 000239 | 000240 | 000241 | 000242 | 000243 | 000244 | 000245 | 000246 | 000247 | 000248 | 000249 | 000250 | 000251 | 000252 | 000253 | 000254 | 000255 | 000256 | 000257 | 000258 | 000259 | 000260 | 000261 | 000262 | 000263 | 000264 | 000265 | 000266 | 000267 | 000268 | 000269 | 000270 | 000271 | 000272 | 000273 | 000274 | 000275 | 000276 | 000277 | 000278 | 000279 | 000280 | 000281 | 000282 | 000283 | 000284 | 000285 | 000286 | 000287 | 000288 | 000289 | 000290 | 000291 | 000292 | 000293 | 000294 | 000295 | 000296 | 000297 | 000298 | 000299 | 000300 | 000301 | 000302 | 000303 | 000304 | 000305 | 000306 | 000307 | 000308 | 000309 | 000310 | 000311 | 000312 | 000313 | 000314 | 000315 | 000316 | 000317 | 000318 | 000319 | 000320 | 000321 | 000322 | 000323 | 000324 | 000325 | 000326 | 000327 | 000328 | 000329 | 000330 | 000331 | 000332 | 000333 | 000334 | 000335 | 000336 | 000337 | 000338 | 000339 | 000340 | 000341 | 000342 | 000343 | 000344 | 000345 | 000346 | 000347 | 000348 | 000349 | 000350 | 000351 | 000352 | 000353 | 000354 | 000355 | 000356 | 000357 | 000358 | 000359 | 000360 | 000361 | 000362 | 000363 | 000364 | 000365 | 000366 | 000367 | 000368 | 000369 | 000370 | 000371 | 000372 | 000373 | 000374 | 000375 | 000376 | 000377 | 000378 | 000379 | 000380 | 000381 | 000382 | 000383 | 000384 | 000385 | 000386 | 000387 | 000388 | 000389 | 000390 | 000391 | 000392 | 000393 | 000394 | 000395 | 000396 | 000397 | 000398 | 000399 | 000400 | 000401 | 000402 | 000403 | 000404 | 000405 | 000406 | 000407 | 000408 | 000409 | 000410 | 000411 | 000412 | 000413 | 000414 | 000415 | 000416 | 000417 | 000418 | 000419 | 000420 | 000421 | 000422 | 000423 | 000424 | 000425 | 000426 | 000427 | 000428 | 000429 | 000430 | 000431 | 000432 | 000433 | 000434 | 000435 | 000436 | 000437 | 000438 | 000439 | 000440 | 000441 | 000442 | 000443 | 000444 | 000445 | 000446 | 000447 | 000448 | 000449 | 000450 | 000451 | 000452 | 000453 | 000454 | 000455 | 000456 | 000457 | 000458 | 000459 | 000460 | 000461 | 000462 | 000463 | 000464 | 000465 | 000466 | 000467 | 000468 | 000469 | 000470 | 000471 | 0 |
|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|---|
|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|--------|---|

```

001277      READ THE COORDINATES ( VERTICES ) OF THE FIELD. FOR THE
001278      DATA TO BE TRANSFORMED
001279
001280      10 LAB=LANCEAD(FLDNAME,VERTCS,FLDINF,NC)
001281      IF (LAB.EQ.0) GO TO 210
001282      IF (LAB.LT.-1) GO TO 10
001283
001284      20
001285      30
001286      31
001287      32
001288      33
001289      34
001290      35
001291      36
001292      37
001293      38
001294      39
001295      40
001296      41
001297      42
001298      43
001299      44
001300      45
001301      46
001302      47
001303      48
001304      49
001305      50
001306      51
001307      52
001308      53
001309      54
001310      55
001311      56
001312      57
001313      58
001314      59
001315      60
001316      61
001317      62
001318      63
001319      64
001320      65
001321      66
001322      67
001323      68
001324      69
001325      70
001326      71
001327      72
001328      73
001329      74
001330      75
001331      76
001332      77
001333      78
001334      79
001335      80
001336      81
001337      82
001338      83
001339      84
001340      85
001341      86
001342      87
001343      88
001344      89
001345      90
001346      91
001347      92
001348      93
001349      94
001350      95
001351      96
001352      97
001353      98
001354      99
001355      100
001356      101
001357      102
001358      103
001359      104
001360      105
001361      106
001362      107
001363      108
001364      109
001365      110
001366      111
001367      112
001368      113
001369      114
001370      115
001371      116
001372      117
001373      118
001374      119
001375      120
001376      121
001377      122
001378      123
001379      124
001380      125
001381      126
001382      127
001383      128
001384      129
001385      130
001386      131
001387      132
001388      133
001389      134
001390      135
001391      136
001392      137
001393      138
001394      139
001395      140
001396      141
001397      142
001398      143
001399      144
001400      145
001401      146
001402      147
001403      148
001404      149
001405      150
001406      151
001407      152
001408      153
001409      154
001410      155
001411      156
001412      157
001413      158
001414      159
001415      160
001416      161
001417      162
001418      163
001419      164
001420      165
001421      166
001422      167
001423      168
001424      169
001425      170
001426      171
001427      172
001428      173
001429      174
001430      175
001431      176
001432      177
001433      178
001434      179
001435      180
001436      181
001437      182
001438      183
001439      184
001440      185
001441      186
001442      187
001443      188
001444      189
001445      190
001446      191
001447      192
001448      193
001449      194
001450      195
001451      196
001452      197
001453      198
001454      199
001455      200
001456      201
001457      202
001458      203
001459      204
001460      205
001461      206
001462      207
001463      208
001464      209
001465      210
001466      211
001467      212
001468      213
001469      214
001470      215
001471      216
001472      217
001473      218
001474      219
001475      220
001476      221
001477      222
001478      223
001479      224
001480      225
001481      226
001482      227
001483      228
001484      229
001485      230
001486      231
001487      232
001488      233
001489      234
001490      235
001491      236
001492      237
001493      238
001494      239
001495      240
001496      241
001497      242
001498      243
001499      244
001500      245
001501      246
001502      247
001503      248
001504      249
001505      250
001506      251
001507      252
001508      253
001509      254
001510      255
001511      256
001512      257
001513      258
001514      259
001515      260
001516      261
001517      262
001518      263
001519      264
001520      265
001521      266
001522      267
001523      268
001524      269
001525      270
001526      271
001527      272
001528      273
001529      274
001530      275
001531      276
001532      277
001533      278
001534      279
001535      280
001536      281
001537      282
001538      283
001539      284
001540      285
001541      286
001542      287
001543      288
001544      289
001545      290
001546      291
001547      292
001548      293
001549      294
001550      295
001551      296
001552      297
001553      298
001554      299
001555      300
001556      301
001557      302
001558      303
001559      304
001560      305
001561      306
001562      307
001563      308
001564      309
001565      310
001566      311
001567      312
001568      313
001569      314
001570      315
001571      316
001572      317
001573      318
001574      319
001575      320
001576      321
001577      322
001578      323
001579      324
001580      325
001581      326
001582      327
001583      328
001584      329
001585      330
001586      331
001587      332
001588      333
001589      334
001590      335
001591      336
001592      337
001593      338
001594      339
001595      340
001596      341
001597      342
001598      343
001599      344
001600      345
001601      346
001602      347
001603      348
001604      349
001605      350
001606      351
001607      352
001608      353
001609      354
001610      355
001611      356
001612      357
001613      358
001614      359
001615      360
001616      361
001617      362
001618      363
001619      364
001620     
```

| ADDRESS | INSTR | OPERAND | COMMENT |
|---------|--------|--|---------|
| 00014 | ALP | SGRT(1) LINES, NSAMP, T/72000) | |
| 00015 | IF | ALP, LC-1, ALP-1 | |
| 00016 | FLD | IMP(1) = FLDIMP(1) | |
| 00017 | FLD | IMP(2) = FLDIMP(2) | |
| 00018 | FLD | IMP(3) = FLDIMP(3) | |
| 00019 | FLD | IMP(4) = FLDIMP(4) | |
| 00020 | FLD | IMP(5) = FLDIMP(5) | |
| 00021 | FLD | IMP(6) = ALP | |
| 00022 | LIN | 5 = FLDIMP(12) = FLDIMP(13) / FLDIMP(3) * 10 | |
| 00023 | MSAR | = FLDIMP(15) = FLDIMP(14) / FLDIMP(6) * 10 | |
| 00024 | CALL | FLDIMP, FLDIMP, FETVEC, NOFLAT | |
| 00025 | DO | 30 1 = 1, LCUMB | |
| 00026 | TOT | PS(1) = 0 | |
| 00027 | DO | 30 J = 1, 101 | |
| 00028 | FLD | IMP(1) = 101 | |
| 00029 | DO | 10 1 = 1, LINES | |
| 00030 | CALL | LIN, MU(1), DATA, END, TAP1 | |
| 00031 | IF | LIN, TAP, MC, 0, 60 TO 170 | |
| 00032 | IF | LIN, MC, 1, 60 TO 90 | |
| 00033 | LIN | FLDIMP(1) | |
| 00034 | DO | 10 TO 50 | |
| 00035 | LIN | ILIN = FLDIMP(3) | |
| 00036 | 58 | CONTINUE | |
| 00037 | CALL | FUL, INTERVCS, MC, FL, ILIN, NSAMP, JJ | |
| 00038 | DO | 10 K = 1, NSAMP | |
| 00039 | KP | (K-1) = FLDIMP(6) + FLDIMP(14) | |
| 00040 | DO | 100 L = 1, J, 2 | |
| 00041 | LKP | 1 = L | |
| 00042 | IF | KP, L, 1, FL, LK, 1, 60 TO 110 | |
| 00043 | IF | KP, 61, FL, LK, 1, 60 TO 90 | |
| 00044 | DO | 60 J = 1, LCOMB | |
| 00045 | AT | J, 0 | |
| 00046 | C | CALL TRANSF TO DO A DATA TRANSFORMATION | |
| 00047 | C | | |
| 00048 | C | CALL TRANSF | |
| 00049 | C | | |
| 00050 | 000224 | | |
| 00051 | 000225 | | |
| 00052 | 000226 | | |
| 00053 | 000227 | | |

[illegible]

| | | | |
|-------|--------|------------------------------|--|
| 00250 | 1020 | 50 TO 100 | ELIMINATE PEROUT/2 OF POINTS FROM UPPER AND LOWER TAILS OF |
| 00251 | 1010 | 90 IF (LAPL-6L-JJ) 60 TO 120 | THE TRANSFORMED DATA DISTRIBUTION --- OBTAIN THE REVISED PLANT |
| 00252 | 1010 | 100 CONTINUE | AND SCALING PARAMETERS CON AND MIN AFTER APPLICATION OF PLANT |
| 00253 | 1010 | 110 CONTINUE | |
| 00254 | 1010 | 120 CONTINUE | |
| 00255 | 1010 | 130 CONTINUE | |
| 00256 | 1010 | 140 CONTINUE | |
| 00257 | 1010 | 150 CONTINUE | |
| 00258 | 1010 | 160 CONTINUE | |
| 00259 | 1010 | 170 CONTINUE | |
| 00260 | 1010 | 180 CONTINUE | |
| 00261 | 1010 | 190 CONTINUE | |
| 00262 | 1010 | 200 CONTINUE | |
| 00263 | 1010 | 210 CONTINUE | |
| 00264 | 1010 | 220 CONTINUE | |
| 00265 | 1010 | 230 CONTINUE | |
| 00266 | 1010 | 240 CONTINUE | |
| 00267 | 1010 | 250 CONTINUE | |
| 00268 | 1010 | 260 CONTINUE | |
| 00269 | 1010 | 270 CONTINUE | |
| 00270 | 1010 | 280 CONTINUE | |
| 00271 | 1010 | 290 CONTINUE | |
| 00272 | 1010 | 300 CONTINUE | |
| 00273 | 1010 | 310 CONTINUE | |
| 00274 | 1010 | 320 CONTINUE | |
| 00275 | 1010 | 330 CONTINUE | |
| 00276 | 1010 | 340 CONTINUE | |
| 00277 | 1010 | 350 CONTINUE | |
| 00278 | 1010 | 360 CONTINUE | |
| 00279 | 1010 | 370 CONTINUE | |
| 00280 | 1010 | 380 CONTINUE | |
| 00281 | 1010 | 390 CONTINUE | |
| 00282 | 1010 | 400 CONTINUE | |
| 00283 | 1010 | 410 CONTINUE | |
| 00284 | 1010 | 420 CONTINUE | |
| 00285 | 1010 | 430 CONTINUE | |
| 00286 | 1010 | 440 CONTINUE | |
| 00287 | 1010 | 450 CONTINUE | |
| 00288 | 1010 | 460 CONTINUE | |
| 00289 | 1010 | 470 CONTINUE | |
| 00290 | 1010 | 480 CONTINUE | |
| 00291 | 1010 | 490 CONTINUE | |
| 00292 | 1010 | 500 CONTINUE | |
| 00293 | 1010 | 510 CONTINUE | |
| 00294 | 1010 | 520 CONTINUE | |
| 00295 | 1010 | 530 CONTINUE | |
| 00296 | 1010 | 540 CONTINUE | |
| 00297 | 1010 | 550 CONTINUE | |
| 00298 | 1010 | 560 CONTINUE | |
| 00299 | 1010 | 570 CONTINUE | |
| 00300 | 1010 | 580 CONTINUE | |
| 00301 | 1010 | 590 CONTINUE | |
| 00302 | 1010 | 600 CONTINUE | |
| 00303 | 1010 | 610 CONTINUE | |
| 00304 | 1010 | 620 CONTINUE | |
| 00305 | 1010 | 630 CONTINUE | |
| 00306 | 1010 | 640 CONTINUE | |
| 00307 | 1010 | 650 CONTINUE | |
| 00308 | 1010 | 660 CONTINUE | |
| 00309 | 1010 | 670 CONTINUE | |
| 00310 | 1010 | 680 CONTINUE | |
| 00311 | 1010 | 690 CONTINUE | |
| 00312 | 1010 | 700 CONTINUE | |
| 00313 | 1010 | 710 CONTINUE | |
| 00314 | 1010 | 720 CONTINUE | |
| 00315 | 1010 | 730 CONTINUE | |
| 00316 | 1010 | 740 CONTINUE | |
| 00317 | 1010 | 750 CONTINUE | |
| 00318 | 1010 | 760 CONTINUE | |
| 00319 | 1010 | 770 CONTINUE | |
| 00320 | 1010 | 780 CONTINUE | |
| 00321 | 1010 | 790 CONTINUE | |
| 00322 | 1010 | 800 CONTINUE | |
| 00323 | 1010 | 810 CONTINUE | |
| 00324 | 1010 | 820 CONTINUE | |
| 00325 | 1010 | 830 CONTINUE | |
| 00326 | 1010 | 840 CONTINUE | |
| 00327 | 1010 | 850 CONTINUE | |
| 00328 | 1010 | 860 CONTINUE | |
| 00329 | 1010 | 870 CONTINUE | |
| 00330 | 1010 | 880 CONTINUE | |
| 00331 | 1010 | 890 CONTINUE | |
| 00332 | 1010 | 900 CONTINUE | |
| 00333 | 1010 | 910 CONTINUE | |
| 00334 | 1010 | 920 CONTINUE | |
| 00335 | 1010 | 930 CONTINUE | |
| 00336 | 1010 | 940 CONTINUE | |
| 00337 | 1010 | 950 CONTINUE | |
| 00338 | 1010 | 960 CONTINUE | |
| 00339 | 1010 | 970 CONTINUE | |
| 00340 | 1010 | 980 CONTINUE | |
| 00341 | 1010 | 990 CONTINUE | |
| 00342 | 1010 | 1000 CONTINUE | |
| 00343 | 1010 | 1010 CONTINUE | |
| 00344 | 1010 | 1020 CONTINUE | |
| 00345 | 1010 | 1030 CONTINUE | |
| 00346 | 1010 | 1040 CONTINUE | |
| 00347 | 1010 | 1050 CONTINUE | |
| 00348 | 1010 | 1060 CONTINUE | |
| 00349 | 1010 | 1070 CONTINUE | |
| 00350 | 1010 | 1080 CONTINUE | |
| 00351 | 1010 | 1090 CONTINUE | |
| 00352 | 1010 | 1100 CONTINUE | |
| 00353 | 1010 | 1110 CONTINUE | |
| 00354 | 1010 | 1120 CONTINUE | |
| 00355 | 1010</ | | |

TAMSONI TAMSONI TAMSONI TAMSONI TAMSONI

Continued on next page

200 CONTINUED

NETOWN THE SCALING PARAMETERS, CON AND MIN : REQUIRED TO
RESCALE THE TRANSFORMED DATA TO THE RANGE : 0 - 255 .

210-RETURN
END

~~ALL INFORMATION CONTAINED HEREIN IS UNCLASSIFIED~~

| SYMBOLIC RELOCATABLE CODE | THINIST THINIST |
|---------------------------------|--------------------|
| 00000000 | 00000000 |
| 00000001 | 00000001 |
| 00000002 | 00000002 |
| 00000003 | 00000003 |
| 00000004 | 00000004 |
| 00000005 | 00000005 |
| 00000006 | 00000006 |
| 00000007 | 00000007 |
| 00000008 | 00000008 |
| 00000009 | 00000009 |
| 0000000A | 0000000A |
| 0000000B | 0000000B |
| 0000000C | 0000000C |
| 0000000D | 0000000D |
| 0000000E | 0000000E |
| 0000000F | 0000000F |
| 00000010 | 00000010 |
| 00000011 | 00000011 |
| 00000012 | 00000012 |
| 00000013 | 00000013 |
| 00000014 | 00000014 |
| 00000015 | 00000015 |
| 00000016 | 00000016 |
| 00000017 | 00000017 |
| 00000018 | 00000018 |
| 00000019 | 00000019 |
| 0000001A | 0000001A |
| 0000001B | 0000001B |
| 0000001C | 0000001C |
| 0000001D | 0000001D |
| 0000001E | 0000001E |
| 0000001F | 0000001F |
| 00000020 | 00000020 |
| 00000021 | 00000021 |
| 00000022 | 00000022 |
| 00000023 | 00000023 |
| 00000024 | 00000024 |
| 00000025 | 00000025 |
| 00000026 | 00000026 |
| 00000027 | 00000027 |
| 00000028 | 00000028 |
| 00000029 | 00000029 |
| 0000002A | 0000002A |
| 0000002B | 0000002B |
| 0000002C | 0000002C |
| 0000002D | 0000002D |
| 0000002E | 0000002E |
| 0000002F | 0000002F |
| 00000030 | 00000030 |
| 00000031 | 00000031 |
| 00000032 | 00000032 |
| 00000033 | 00000033 |
| 00000034 | 00000034 |
| 00000035 | 00000035 |
| 00000036 | 00000036 |
| 00000037 | 00000037 |
| 00000038 | 00000038 |
| 00000039 | 00000039 |
| 0000003A | 0000003A |
| 0000003B | 0000003B |
| 0000003C | 0000003C |
| 0000003D | 0000003D |
| 0000003E | 0000003E |
| 0000003F | 0000003F |
| 00000040 | 00000040 |
| 00000041 | 00000041 |
| 00000042 | 00000042 |
| 00000043 | 00000043 |
| 00000044 | 00000044 |
| 00000045 | 00000045 |
| 00000046 | 00000046 |
| 00000047 | 00000047 |
| 00000048 | 00000048 |
| 00000049 | 00000049 |
| 0000004A | 0000004A |
| 0000004B | 0000004B |
| 0000004C | 0000004C |
| 0000004D | 0000004D |
| 0000004E | 0000004E |
| 0000004F | 0000004F |
| 00000050 | 00000050 |
| 00000051 | 00000051 |
| 00000052 | 00000052 |
| 00000053 | 00000053 |
| 00000054 | 00000054 |
| 00000055 | 00000055 |
| 00000056 | 00000056 |
| 00000057 | 00000057 |
| 00000058 | 00000058 |
| 00000059 | 00000059 |
| 0000005A | 0000005A |
| 0000005B | 0000005B |
| 0000005C | 0000005C |
| 0000005D | 0000005D |
| 0000005E | 0000005E |
| 0000005F | 0000005F |
| 00000060 | 00000060 |
| 00000061 | 00000061 |
| 00000062 | 00000062 |
| 00000063 | 00000063 |
| 00000064 | 00000064 |
| 00000065 | 00000065 |
| 00000066 | 00000066 |
| 00000067 | 00000067 |
| 00000068 | 00000068 |
| 00000069 | 00000069 |
| 0000006A | 0000006A |
| 0000006B | 0000006B |
| 0000006C | 0000006C |
| 0000006D | 0000006D |
| 0000006E | 0000006E |
| 0000006F | 0000006F |
| 00000070 | 00000070 |
| 00000071 | 00000071 |
| 00000072 | 00000072 |
| 00000073 | |

| | | | | | | |
|-----------|----------|---|----------|----|-----|------------|
| 26 APR 77 | 10125117 | 0 | 02735059 | 19 | 197 | (05111101) |
| 26 APR 77 | 10125117 | 1 | 02791900 | 30 | 1 | (05111101) |
| 26 APR 77 | 10125117 | 0 | 02791132 | 19 | 30 | (05111101) |

0 FOR INTRAW-LINER
UNITAL 1 LOS FORTRAN V
THIS COMPILATION WAS
CIRC 11 LEVEL 25A - EXEC LEVEL 212010010A)
DONE ON 04 MAY 77 AT 22:09:50

ALL VINEYARD

228-715

SUBROUTINE LNTTRAN ENTRY POINT 002977

STORAGE-USED-CODE177-002675F-DATA(8)-B213111-BLANK COMMON(2)-000000-

CUMMION BLOCKS:

0603
400004
0703

INFORM 00154
INMILC 00096
LUNAL 00075

EXTRANEAL REFERENCES (BLOCK, NAME)

| | |
|-------|--------|
| 00004 | TAPKUM |
| 00007 | LAKCAD |
| 00010 | PLONT |
| 00011 | PRIMOR |
| 00012 | LINEMT |
| 00013 | PLINT |
| 00014 | TRANSF |
| 00015 | IRILIM |
| 00016 | RTMANF |
| 00017 | COMST |
| 00020 | NADUS |
| 00021 | NIUS |
| 00023 | NIUS |
| 00024 | NIUS |
| 00025 | NIUS |
| 00026 | NIUS |
| 00027 | NIUS |
| 00028 | NIUS |
| 00029 | NIUS |
| 00030 | NIUS |
| 00031 | NIUS |
| 00032 | NIUS |
| 00033 | NIUS |
| 00034 | NIUS |
| 00035 | NIUS |
| 00036 | NIUS |
| 00037 | NIUS |
| 00038 | NIUS |
| 00039 | NIUS |
| 00040 | NIUS |
| 00041 | NIUS |
| 00042 | NIUS |
| 00043 | NIUS |
| 00044 | NIUS |
| 00045 | NIUS |
| 00046 | NIUS |
| 00047 | NIUS |
| 00048 | NIUS |
| 00049 | NIUS |
| 00050 | NIUS |
| 00051 | NIUS |
| 00052 | NIUS |
| 00053 | NIUS |
| 00054 | NIUS |
| 00055 | NIUS |
| 00056 | NIUS |
| 00057 | NIUS |
| 00058 | NIUS |
| 00059 | NIUS |
| 00060 | NIUS |
| 00061 | NIUS |
| 00062 | NIUS |
| 00063 | NIUS |
| 00064 | NIUS |
| 00065 | NIUS |
| 00066 | NIUS |
| 00067 | NIUS |
| 00068 | NIUS |
| 00069 | NIUS |
| 00070 | NIUS |
| 00071 | NIUS |
| 00072 | NIUS |
| 00073 | NIUS |
| 00074 | NIUS |
| 00075 | NIUS |
| 00076 | NIUS |
| 00077 | NIUS |
| 00078 | NIUS |
| 00079 | NIUS |
| 00080 | NIUS |
| 00081 | NIUS |
| 00082 | NIUS |
| 00083 | NIUS |
| 00084 | NIUS |
| 00085 | NIUS |
| 00086 | NIUS |
| 00087 | NIUS |
| 00088 | NIUS |
| 00089 | NIUS |
| 00090 | NIUS |
| 00091 | NIUS |
| 00092 | NIUS |
| 00093 | NIUS |
| 00094 | NIUS |
| 00095 | NIUS |
| 00096 | NIUS |
| 00097 | NIUS |
| 00098 | NIUS |
| 00099 | NIUS |
| 00100 | NIUS |

STORAGE ASSIGNMENT (BLOCK, TYPE, RELATIVE LOCATION, NAME)[illegible][illegible]

00101 10 SURROUTIME LMTNMI10ATA,MAL,MIM.COM,BHATLALCOMB,BMTN16,SCAF6,
00101 20 PEROUT,FILM15,10P.LAM,FLUNAN,MC,VERTCS, MESSAL, BIAS,
00101 30 MF , NPUM !
LMTN001
LMTN002
LMTN003

```

00101 IF SCALF6 = 1 . RESCALE BY HISTOGRAM METHOD
00102 IF SCALF6 = 2 . RESCALE BY THE STATISTICS METHOD
00103 IF SCALF6 = 3 . RESCALE WITH USER-INPUT SCALING PARAMETERS
00104
00105 NOTE: IF THE FLAG, RESCAL, PEGD07 IS 2, NO RESCALING IS
00106 PERFORMED. HOWEVER, PEGD07 IS APPLIED TO THE TRANSFORMED
00107 DATA DISTRIBUTION PRIOR TO FINAL OUTPUT OF TRANSFORMED
00108 DATA VALUES.
00109
00110 IMPLICIT INTEGER(4)
00111 REAL DIM(100), MAX(100), MIN(100), N(100), N(100)
00112 REAL NORM(100), NORM(100), SUM, CUT
00113 REAL N(100)
00114
00115 REAL DIM(100), AC(100), AT(100), T(100), MP(100), MP(100)
00116
00117
00118
00119
00120
00121
00122
00123
00124
00125

```

```

00101 IF SCALF6 = 1 . RESCALE BY HISTOGRAM METHOD
00102 IF SCALF6 = 2 . RESCALE BY THE STATISTICS METHOD
00103 IF SCALF6 = 3 . RESCALE WITH USER-INPUT SCALING PARAMETERS
00104
00105 NOTE: IF THE FLAG, RESCAL, PEGD07 IS 2, NO RESCALING IS
00106 PERFORMED. HOWEVER, PEGD07 IS APPLIED TO THE TRANSFORMED
00107 DATA DISTRIBUTION PRIOR TO FINAL OUTPUT OF TRANSFORMED
00108 DATA VALUES.
00109
00110 IMPLICIT INTEGER(4)
00111 REAL DIM(100), MAX(100), MIN(100), N(100), N(100)
00112 REAL NORM(100), NORM(100), SUM, CUT
00113 REAL N(100)
00114
00115 REAL DIM(100), AC(100), AT(100), T(100), MP(100), MP(100)
00116
00117
00118
00119
00120
00121
00122
00123
00124
00125

```

ORIGINAL PAGE IS
OF POOR QUALITY


```

00137 MISCL,MISAL,IMPUM,CHIMP,ENPAB,MAPUNT,MAPFILE,
00138 DRUMAD,DMHROS,PAGSIZ,DATAFIL,STAFIL,ASAV,ASAVFL
00139 IF IRESCAL=EV.01 GO TO 50
00140 END
00141 IF IRESCAL=EV.01 GO TO 50
00142 CHECK FOR RESCALE FACTORS INPUT BY USER ( SCAFL6 = 3 )
00143 IF (SCAFL6=NE.3) GO TO 20
00144 COMPUTE THE TRANSFORMED DATA MAX, USING INPUT
00145 SCALING PARAMETERS ( CON AND MIN )
00146 DO 10 KF=1,LCONB
00147 MAX(KF) = 255.7 (CON(KF) * MIN(KF)
00148 10 CONTINUE
00149 20 CONTINUE
00150 COMPUTE THE OUTPUT HISTOGRAM SCALE FACTOR, ACON
00151 ACON(KK) = (MAX(KK) - MIN(KK)) / 80
00152
00153
00154
00155
00156
00157

```

LNTK0049
 LNTK0050
 LNTK0051
 LNTK0052
 LNTK0053
 LNTK0054
 LNTK0055
 LNTK0056
 LNTK0057
 LNTK0058
 LNTK0059
 LNTK0060
 LNTK0061
 LNTK0062
 LNTK0063
 LNTK0064
 LNTK0065
 LNTK0066

LNTK0067
 LNTK0068
 LNTK0069
 LNTK0070
 LNTK0071
 LNTK0072
 LNTK0073
 LNTK0074
 LNTK0075
 LNTK0076
 LNTK0077
 LNTK0078
 LNTK0079
 LNTK0080
 LNTK0081
 LNTK0082
 LNTK0083
 LNTK0084
 LNTK0085
 LNTK0086
 LNTK0087
 LNTK0088
 LNTK0089
 LNTK0090
 LNTK0091
 LNTK0092
 LNTK0093
 LNTK0094
 LNTK0095
 LNTK0096
 LNTK0097
 LNTK0098
 LNTK0099
 LNTK0100
 LNTK0101
 LNTK0102

ORIGINAL PAGE
 OF POOR QUALITY

```

00160 30 FETVC2(KK)=KK
00161 IF (SCAFL6=EV.1) GO TO 80
00162 FOR STATISTICAL OR INPUT SCALE PARAMETERS, SAVE THE INITIAL
00163 SCALING PARAMETERS ( MIN, MAX, CON ) FOR RE-INITIALIZATION
00164 OF THESE PARAMETERS ON THE SECOND AND SUCCEEDING FIELDS TO BE
00165 INPUT, TRANSFORMED, AND RE-SCALED ( IF RESCAL GT 0 )
00166 DO 40 KK=1,LCONB
00167 MAX(KK) = MAX(KK)
00168 MIN(KK) = MIN(KK)
00169 40 CONSAV(KK) = CON(KK)
00170 POSITION THE INPUT DATA FILE, AND READ IN THE HEADER RECORD
00171 50 CONTINUE
00172 CALL TAPHDN( DATAPE, DATAFIL )
00173 READ THE COORDINATES ( VERTICES ) OF THE FIELD FOR THE DATA
00174 TO BE TRANSFORMED
00175 60 LAM=LANEADIFLONAM,VERTICES,FLODIMP,NCI
00176 IF (LANEADIFLONAM=0) GO TO 920
00177 IF (LANEADIFLONAM=0) GO TO 920
00178 FOR STATISTICAL OR INPUT SCALING PARAMETERS, INITIALIZE THE
00179 SCALING PARAMETERS MAX, MIN, CON, ACON FOR THIS FIELD
00180 IF IRESCAL=EV.01 GO TO 80
00181
00182
00183
00184
00185
00186

```



```

00327 1830 PAUMAX(1) = 0
00328 1835 PAUMIN(1) = 0
00329 1840 PAUM(1) = 0
00330 1845 TUPPTS(17) = 0
00331 1850 TRIM(1) = 1.0E35
00332 1855 TRAX(1) = -1.0E35
00333 1860 TRUN(1) = AICOM(1)
00334 1865 DO 160 J=1,101
00335 1870 FLMIS(1:J) = 0
00336 1875 CONTINUE
00337 1880
00338 1885 LSTLIN=0
00339 1890 M=0
00340 1895 IF (M.GT.LINEST) GO TO 350
00341 1900 M=M+1
00342 1905 HEAD ONE SCAN LINE OF DATA FROM THE INPUT TAPE
00343 1910
00344 1915 CALL LIREROT(DATA,ENOTAP)
00345 1920 IF (ENDTAP.NE.D) GO TO 350
00346 1925
00347 1930
00348 1935
00349 1940
00350 1945
00351 1950
00352 1955
00353 1960
00354 1965
00355 1970
00356 1975
00357 1980
00358 1985
00359 1990
00360 1995
00361 2000
00362 2005
00363 2010
00364 2015
00365 2020
00366 2025
00367 2030
00368 2035
00369 2040
00370 2045
00371 2050

```

LNTMU161
 LNTMU162
 LNTMU163
 LNTMU164
 LNTMU165
 LNTMU166
 LNTMU167
 LNTMU168
 LNTMU169
 LNTMU170
 LNTMU171
 LNTMU172
 LNTMU173
 LNTMU174
 LNTMU175
 LNTMU176
 LNTMU177
 LNTMU178
 LNTMU179
 LNTMU180
 LNTMU181
 LNTMU182

```

00326 1830 IF (M.NE.1) GO TO 190
00327 1835 ILM=FLDINF(1)
00328 1840 GO TO 200
00329 1845
00330 1850 ILM=ILIN*FLINF(1)
00331 1855 CONTINUE
00332 1860
00333 1865
00334 1870
00335 1875
00336 1880
00337 1885
00338 1890
00339 1895
00340 1900
00341 1905
00342 1910
00343 1915
00344 1920
00345 1925
00346 1930
00347 1935
00348 1940
00349 1945
00350 1950
00351 1955
00352 1960
00353 1965
00354 1970
00355 1975
00356 1980
00357 1985
00358 1990
00359 1995
00360 2000
00361 2005
00362 2010
00363 2015
00364 2020
00365 2025
00366 2030
00367 2035
00368 2040
00369 2045
00370 2050
00371 2055

```

LNTMU183
 LNTMU184
 LNTMU185
 LNTMU186
 LNTMU187
 LNTMU188
 LNTMU189
 LNTMU190
 LNTMU191
 LNTMU192
 LNTMU193
 LNTMU194
 LNTMU195
 LNTMU196
 LNTMU197
 LNTMU198
 LNTMU199
 LNTMU200
 LNTMU201
 LNTMU202
 LNTMU203
 LNTMU204
 LNTMU205
 LNTMU206
 LNTMU207
 LNTMU208
 LNTMU209
 LNTMU210
 LNTMU211
 LNTMU212
 LNTMU213
 LNTMU214
 LNTMU215
 LNTMU216
 LNTMU217
 LNTMU218

| | | | |
|-------|------|---|----------|
| 00373 | 2170 | GO 300 101, LLOMB | LN1HU217 |
| 00376 | 2200 | IF (AT111 - LT, THMIN11) THMAX11 = AT111 | LN1HU218 |
| 00400 | 2220 | IF (AT111 - LT, THMIN11) THMAX11 = AT111 | LN1HU219 |
| 00400 | 2230 | IF RESCAL = 0 NO RESCALING IS APPLIED. OTHER WISE RESCALE | LN1HU220 |
| 00400 | 2240 | USING SCALING PARAMETERS OBTAINED FROM EITHER HISTOGRAM | LN1HU221 |
| 00400 | 2250 | STATISTICS. OR USER-INPUT 1 SCALF6 = 1. 2. ON 3. | LN1HU222 |
| 00400 | 2260 | IF (RESCAL - GT, 0) GO TO 260 | LN1HU223 |
| 00402 | 2280 | IF TRANSFORMED DATA IS NOT RECALLED | LN1HU224 |
| 00402 | 2300 | TEST FOR OUT- OF - RANGE TRANSFORMED VALUES | LN1HU225 |
| 00402 | 2310 | SET = 0 ANY VALUE LESS THAN 0, OR LESS THAN THE NEW MIN | LN1HU226 |
| 00402 | 2320 | AFTER APPLICATION OF PEROUT | LN1HU227 |
| 00402 | 2330 | SET = 255 ANY VALUE GREATER THAN 255, OR GREATER THAN | LN1HU228 |
| 00402 | 2340 | THE NEW MAX AFTER APPLICATION OF PEROUT | LN1HU229 |
| 00402 | 2350 | IF (AT111 - LT - NEWMIN11) GO TO 230 | LN1HU230 |
| 00404 | 2360 | | LN1HU231 |

| | | | |
|-------|------|--|----------|
| 00404 | 2410 | IF (AT111 - GT - NEWMAX11) GO TO 240 | LN1HU232 |
| 00410 | 2420 | GO TO 250 | LN1HU233 |
| 00410 | 2430 | IF (MTRN - EQ, 0) BADMIN11 = BADMIN11 + 1 | LN1HU234 |
| 00413 | 2440 | AT111 = 0.0 | LN1HU235 |
| 00415 | 2450 | GO TO 250 | LN1HU236 |
| 00417 | 2460 | IF (MINAN - EQ, 0) BADMAX11 = BADMAX11 + 1 | LN1HU237 |
| 00420 | 2470 | AT111 = 255. | LN1HU238 |
| 00420 | 2480 | 250 CONTINUE | LN1HU239 |
| 00420 | 2490 | | LN1HU240 |
| 00420 | 2500 | | LN1HU241 |
| 00420 | 2510 | | LN1HU242 |
| 00420 | 2520 | | LN1HU243 |
| 00420 | 2530 | | LN1HU244 |
| 00421 | 2540 | DPT = AT111 / MAXCON + 1.1 | LN1HU245 |
| 00422 | 2550 | TOTPTS11 = TOTPTS11 + 1 | LN1HU246 |
| 00422 | 2560 | IF (DPT - GT, 101) DPT = 101 | LN1HU247 |
| 00425 | 2570 | IF (DPT - LE, 0) DPT = 1 | LN1HU248 |
| 00427 | 2580 | FILMIS11 - DPT = FILMIS11 - DPT + 1 | LN1HU249 |
| 00430 | 2590 | 251 = AT111 + 0.5 | LN1HU250 |
| 00430 | 2600 | GO TO 300 | LN1HU251 |
| 00432 | 2610 | 260 CONTINUE | LN1HU252 |
| 00433 | 2620 | | LN1HU253 |
| 00433 | 2630 | | LN1HU254 |
| 00433 | 2640 | | LN1HU255 |
| 00433 | 2650 | | LN1HU256 |
| 00434 | 2660 | | LN1HU257 |
| 00434 | 2670 | | LN1HU258 |
| 00434 | 2680 | | LN1HU259 |
| 00434 | 2690 | | LN1HU260 |
| 00440 | 2700 | IF (AT111 - LT - MIN11) GO TO 270 | LN1HU261 |
| 00441 | 2710 | IF (AT111 - GT - MAX11) GO TO 280 | LN1HU262 |
| 00441 | 2720 | IF (AT111 - GT - MAX11) GO TO 280 | LN1HU263 |
| 00442 | 2730 | IF (AT111 - GT - MAX11) GO TO 280 | LN1HU264 |
| 00442 | 2740 | IF (DPT - LE, 0) DPT = 1 | LN1HU265 |
| 00444 | 2750 | IF (DPT - GT, 101) DPT = 101 | LN1HU266 |
| 00444 | 2760 | GO TO 290 | LN1HU267 |

```

00477 2770 C 270 OPT = ABS( MINUT - XT(1) ) / ACUNT(1)
00478 2780 C OPT = 10 - OPT
00479 2790 C
00480 2800 C PHIN(1) = PMINUT * 1
00481 2810 IF (OPT .LE. 0) OPT = 1
00482 2820 YREAL(1) = 0
00483 2830 GO TO 290
00484 2840 C
00485 2850 C 280 OPT = ABS( XT(1) - MAX(1) ) / XCONT(1)
00486 2860 C
00487 2870 C OPT = OPT + 1
00488 2880 C
00489 2890 C PHAX(1) = PMAX(1) * 1
00490 2900 IF (OPT .GT. 10) OPT = 101
00491 2910 YREAL(1) = 255
00492 2920 C
00493 2930 C 290 TOTPS(1) = 1 - TOTPS(1)
00494 2940 FILMS(1) = OPT / FILMS(1) * OPT
00495 2950 ZSAMP(1) = 1 - ZSAMP(1)
00496 2960 YZSAMP(1) = YREAL(1) * 0.5
00497 2970 C
00498 2980 C 300 CONTINUE
00499 2990 GO TO 330
00500 3000 C
00501 3010 C 310 IF (JUMP(1) .GE. 1) GO TO 340
00502 3020 C
00503 3030 C
00504 3040 C
00505 3050 C
00506 3060 C
00507 3070 C
00508 3080 C
00509 3090 C
00510 3100 C
00511 3110 C
00512 3120 C
00513 3130 C
00514 3140 C
00515 3150 C
00516 3160 C
00517 3170 C
00518 3180 C
00519 3190 C
00520 3200 C
00521 3210 C
00522 3220 C
00523 3230 C
00524 3240 C
00525 3250 C
00526 3260 C
00527 3270 C
00528 3280 C
00529 3290 C
00530 3300 C
00531 3310 C
00532 3320 C
00533 3330 C

```

```

00475 2990 C 320 CONTINUE
00476 3000 C 330 CONTINUE
00501 3010 C 340 CONTINUE
00502 3020 C IF (IM(1) .EQ. 1) LSTLIN = 1
00503 3030 C
00504 3040 C
00505 3050 C
00506 3060 C
00507 3070 C
00508 3080 C
00509 3090 C
00510 3100 C
00511 3110 C
00512 3120 C
00513 3130 C
00514 3140 C
00515 3150 C
00516 3160 C
00517 3170 C
00518 3180 C
00519 3190 C
00520 3200 C
00521 3210 C
00522 3220 C
00523 3230 C
00524 3240 C
00525 3250 C
00526 3260 C
00527 3270 C
00528 3280 C
00529 3290 C
00530 3300 C
00531 3310 C
00532 3320 C
00533 3330 C

```

ORIGINAL PAGE IS
OF POOR QUALITY

| | | | |
|-------|------|-------------------------------|----------|
| 00529 | 3250 | SUM = 0.0 | LNIN0329 |
| 00530 | 3250 | DU 370 J-1.101.1 | LNIN0330 |
| 00531 | 3250 | IF (SUM-GE-CUT) GO TO 360 | LNIN0331 |
| 00532 | 3250 | GO TO 370 | LNIN0332 |
| 00533 | 3250 | MINCUT11 = SUM | LNIN0333 |
| 00534 | 3250 | MEMIN11 = (J-1) * NICON * 0.5 | LNIN0334 |
| 00535 | 3250 | GO TO 380 | LNIN0335 |
| 00536 | 3250 | | LNIN0336 |
| 00537 | 3250 | | LNIN0337 |
| 00538 | 3250 | | LNIN0338 |
| 00539 | 3250 | | LNIN0339 |
| 00540 | 3250 | | LNIN0340 |
| 00541 | 3250 | | LNIN0341 |
| 00542 | 3250 | | LNIN0342 |
| 00543 | 3250 | | LNIN0343 |
| 00544 | 3250 | | LNIN0344 |
| 00545 | 3250 | | LNIN0345 |
| 00546 | 3250 | | LNIN0346 |
| 00547 | 3250 | | LNIN0347 |
| 00548 | 3250 | | LNIN0348 |
| 00549 | 3250 | | LNIN0349 |
| 00550 | 3250 | | LNIN0350 |
| 00551 | 3250 | | LNIN0351 |
| 00552 | 3250 | | LNIN0352 |
| 00553 | 3250 | | LNIN0353 |
| 00554 | 3250 | | LNIN0354 |
| 00555 | 3250 | | LNIN0355 |
| 00556 | 3250 | | LNIN0356 |
| 00557 | 3250 | | LNIN0357 |
| 00558 | 3250 | | LNIN0358 |
| 00559 | 3250 | | LNIN0359 |
| 00560 | 3250 | | LNIN0360 |
| 00561 | 3250 | | LNIN0361 |
| 00562 | 3250 | | LNIN0362 |
| 00563 | 3250 | | LNIN0363 |
| 00564 | 3250 | | LNIN0364 |
| 00565 | 3250 | | LNIN0365 |
| 00566 | 3250 | | LNIN0366 |
| 00567 | 3250 | | LNIN0367 |
| 00568 | 3250 | | LNIN0368 |
| 00569 | 3250 | | LNIN0369 |
| 00570 | 3250 | | LNIN0370 |
| 00571 | 3250 | | LNIN0371 |
| 00572 | 3250 | | LNIN0372 |
| 00573 | 3250 | | LNIN0373 |
| 00574 | 3250 | | LNIN0374 |
| 00575 | 3250 | | LNIN0375 |
| 00576 | 3250 | | LNIN0376 |
| 00577 | 3250 | | LNIN0377 |
| 00578 | 3250 | | LNIN0378 |
| 00579 | 3250 | | LNIN0379 |
| 00580 | 3250 | | LNIN0380 |
| 00581 | 3250 | | LNIN0381 |
| 00582 | 3250 | | LNIN0382 |
| 00583 | 3250 | | LNIN0383 |
| 00584 | 3250 | | LNIN0384 |
| 00585 | 3250 | | LNIN0385 |
| 00586 | 3250 | | LNIN0386 |
| 00587 | 3250 | | LNIN0387 |
| 00588 | 3250 | | LNIN0388 |
| 00589 | 3250 | | LNIN0389 |
| 00590 | 3250 | | LNIN0390 |
| 00591 | 3250 | | LNIN0391 |
| 00592 | 3250 | | LNIN0392 |

| | | | |
|-------|------|--------------------------------------|----------|
| 00560 | 3570 | 930 NPER1 = PEROUT * .01 * .001 | LNIN0357 |
| 00561 | 3580 | 930 NPER2 = PEROUT * .01 * .001 | LNIN0358 |
| 00562 | 3590 | | LNIN0359 |
| 00563 | 3600 | RSET=0 | LNIN0360 |
| 00564 | 3610 | IG=0 | LNIN0361 |
| 00565 | 3620 | IR=0 | LNIN0362 |
| 00566 | 3630 | IE=0 | LNIN0363 |
| 00567 | 3640 | IA=0 | LNIN0364 |
| 00568 | 3650 | | LNIN0365 |
| 00569 | 3660 | DO 500 I=1,LCOM | LNIN0366 |
| 00570 | 3670 | MATOT=TOTPIS(I)NPER1 | LNIN0367 |
| 00571 | 3680 | MITOT=TOTPIS(I)NPER2 | LNIN0368 |
| 00572 | 3690 | IF (PRIM1(I).GT.MATOT) GO TO 440 | LNIN0369 |
| 00573 | 3700 | GO TO 440 | LNIN0370 |
| 00574 | 3710 | C RESET MIN SMALLER | LNIN0371 |
| 00575 | 3720 | 940 CHIN=PRIM1(I) | LNIN0372 |
| 00576 | 3730 | DO 450 J=1,10.1.1 | LNIN0373 |
| 00577 | 3740 | IG=10.1 | LNIN0374 |
| 00578 | 3750 | CHIN=CHIN-FILMIS(I,J) | LNIN0375 |
| 00579 | 3760 | IF (CHIN.GT.MATOT) GO TO 450 | LNIN0376 |
| 00580 | 3770 | IF (CHIN.LT.MITOT) IG=10.1 | LNIN0377 |
| 00581 | 3780 | RSET=1 | LNIN0378 |
| 00582 | 3790 | MIN11=MIN11-IGACON(I) | LNIN0379 |
| 00583 | 3800 | IG=0 | LNIN0380 |
| 00584 | 3810 | GO TO 490 | LNIN0381 |
| 00585 | 3820 | 950 CONTINUE | LNIN0382 |
| 00586 | 3830 | 960 IF (PRIM1(I).LT.MITOT) GO TO 470 | LNIN0383 |
| 00587 | 3840 | GO TO 490 | LNIN0384 |
| 00588 | 3850 | C RESET MIN LARGER | LNIN0385 |
| 00589 | 3860 | 970 CHIN=PRIM1(I) | LNIN0386 |
| 00590 | 3870 | DO 400 J=1,1.91 | LNIN0387 |
| 00591 | 3880 | IR=10.1 | LNIN0388 |
| 00592 | 3890 | CHIN=CHIN+FILMIS(I,J) | LNIN0389 |
| 00593 | 3900 | IF (CHIN.LT.MITOT) GO TO 480 | LNIN0390 |
| 00594 | 3910 | IF (CHIN.GT.MATOT) IR=10.1 | LNIN0391 |
| 00595 | 3920 | MIN11=MIN11-IGACON(I) | LNIN0392 |


```

00774 1210
00775 1211
00776 1212
00777 1213
00778 1214
00779 1215
00780 1216
00781 1217
00782 1218
00783 1219
00784 1220
00785 1221
00786 1222
00787 1223
00788 1224
00789 1225
00790 1226
00791 1227
00792 1228
00793 1229
00794 1230
00795 1231
00796 1232
00797 1233
00798 1234
00799 1235
00800 1236
00801 1237
00802 1238
00803 1239
00804 1240
00805 1241
00806 1242
00807 1243
00808 1244
00809 1245
00810 1246
00811 1247
00812 1248
00813 1249
00814 1250
00815 1251
00816 1252
00817 1253
00818 1254
00819 1255
00820 1256
00821 1257
00822 1258
00823 1259
00824 1260
00825 1261
00826 1262
00827 1263
00828 1264
00829 1265
00830 1266
00831 1267
00832 1268
00833 1269
00834 1270
00835 1271
00836 1272
00837 1273
00838 1274
00839 1275
00840 1276
00841 1277
00842 1278
00843 1279
00844 1280
00845 1281
00846 1282
00847 1283
00848 1284
00849 1285
00850 1286
00851 1287
00852 1288
00853 1289
00854 1290
00855 1291
00856 1292
00857 1293
00858 1294
00859 1295
00860 1296
00861 1297
00862 1298
00863 1299
00864 1300
00865 1301
00866 1302
00867 1303
00868 1304
00869 1305
00870 1306
00871 1307
00872 1308
00873 1309
00874 1310
00875 1311
00876 1312
00877 1313
00878 1314
00879 1315
00880 1316
00881 1317
00882 1318
00883 1319
00884 1320
00885 1321
00886 1322
00887 1323
00888 1324
00889 1325
00890 1326
00891 1327
00892 1328
00893 1329
00894 1330
00895 1331
00896 1332
00897 1333
00898 1334
00899 1335
00900 1336
00901 1337
00902 1338
00903 1339
00904 1340
00905 1341
00906 1342
00907 1343
00908 1344
00909 1345
00910 1346
00911 1347
00912 1348
00913 1349
00914 1350
00915 1351
00916 1352
00917 1353
00918 1354
00919 1355
00920 1356
00921 1357
00922 1358
00923 1359
00924 1360
00925 1361
00926 1362
00927 1363
00928 1364
00929 1365
00930 1366
00931 1367
00932 1368
00933 1369
00934 1370
00935 1371
00936 1372
00937 1373
00938 1374
00939 1375
00940 1376
00941 1377
00942 1378
00943 1379
00944 1380
00945 1381
00946 1382
00947 1383
00948 1384
00949 1385
00950 1386
00951 1387
00952 1388
00953 1389
00954 1390
00955 1391
00956 1392
00957 1393
00958 1394
00959 1395
00960 1396
00961 1397
00962 1398
00963 1399
00964 1400
00965 1401
00966 1402
00967 1403
00968 1404
00969 1405
00970 1406
00971 1407
00972 1408
00973 1409
00974 1410
00975 1411
00976 1412
00977 1413
00978 1414
00979 1415
00980 1416
00981 1417
00982 1418
00983 1419
00984 1420
00985 1421
00986 1422
00987 1423
00988 1424
00989 1425
00990 1426
00991 1427
00992 1428
00993 1429
00994 1430
00995 1431
00996 1432
00997 1433
00998 1434
00999 1435

```

```

00900 1436
00901 1437
00902 1438
00903 1439
00904 1440
00905 1441
00906 1442
00907 1443
00908 1444
00909 1445
00910 1446
00911 1447
00912 1448
00913 1449
00914 1450
00915 1451
00916 1452
00917 1453
00918 1454
00919 1455
00920 1456
00921 1457
00922 1458
00923 1459
00924 1460
00925 1461
00926 1462
00927 1463
00928 1464
00929 1465
00930 1466
00931 1467
00932 1468
00933 1469
00934 1470
00935 1471
00936 1472
00937 1473
00938 1474
00939 1475
00940 1476
00941 1477
00942 1478
00943 1479
00944 1480
00945 1481
00946 1482
00947 1483
00948 1484
00949 1485
00950 1486
00951 1487
00952 1488
00953 1489
00954 1490
00955 1491
00956 1492
00957 1493
00958 1494
00959 1495
00960 1496
00961 1497
00962 1498
00963 1499
00964 1500
00965 1501
00966 1502
00967 1503
00968 1504
00969 1505
00970 1506
00971 1507
00972 1508
00973 1509
00974 1510
00975 1511
00976 1512
00977 1513
00978 1514
00979 1515
00980 1516
00981 1517
00982 1518
00983 1519
00984 1520
00985 1521
00986 1522
00987 1523
00988 1524
00989 1525
00990 1526
00991 1527
00992 1528
00993 1529
00994 1530
00995 1531
00996 1532
00997 1533
00998 1534
00999 1535

```

```

01000 1536
01001 1537
01002 1538
01003 1539
01004 1540
01005 1541
01006 1542
01007 1543
01008 1544
01009 1545
01010 1546
01011 1547
01012 1548
01013 1549
01014 1550
01015 1551
01016 1552
01017 1553
01018 1554
01019 1555
01020 1556
01021 1557
01022 1558
01023 1559
01024 1560
01025 1561
01026 1562
01027 1563
01028 1564
01029 1565
01030 1566
01031 1567
01032 1568
01033 1569
01034 1570
01035 1571
01036 1572
01037 1573
01038 1574
01039 1575
01040 1576
01041 1577
01042 1578
01043 1579
01044 1580
01045 1581
01046 1582
01047 1583
01048 1584
01049 1585
01050 1586
01051 1587
01052 1588
01053 1589
01054 1590
01055 1591
01056 1592
01057 1593
01058 1594
01059 1595
01060 1596
01061 1597
01062 1598
01063 1599
01064 1600
01065 1601
01066 1602
01067 1603
01068 1604
01069 1605
01070 1606
01071 1607
01072 1608
01073 1609
01074 1610
01075 1611
01076 1612
01077 1613
01078 1614
01079 1615
01080 1616
01081 1617
01082 1618
01083 1619
01084 1620
01085 1621
01086 1622
01087 1623
01088 1624
01089 1625
01090 1626
01091 1627
01092 1628
01093 1629
01094 1630
01095 1631
01096 1632
01097 1633
01098 1634
01099 1635
01100 1636
01101 1637
01102 1638
01103 1639
01104 1640
01105 1641
01106 1642
01107 1643
01108 1644
01109 1645
01110 1646
01111 1647
01112 1648
01113 1649
01114 1650
01115 1651
01116 1652
01117 1653
01118 1654
01119 1655
01120 1656
01121 1657
01122 1658
01123 1659
01124 1660
01125 1661
01126 1662
01127 1663
01128 1664
01129 1665
01130 1666
01131 1667
01132 1668
01133 1669
01134 1670
01135 1671
01136 1672
01137 1673
01138 1674
01139 1675
01140 1676
01141 1677
01142 1678
01143 1679
01144 1680
01145 1681
01146 1682
01147 1683
01148 1684
01149 1685
01150 1686
01151 1687
01152 1688
01153 1689
01154 1690
01155 1691
01156 1692
01157 1693
01158 1694
01159 1695
01160 1696
01161 1697
01162 1698
01163 1699
01164 1700
01165 1701
01166 1702
01167 1703
01168 1704
01169 1705
01170 1706
01171 1707
01172 1708
01173 1709
01174 1710
01175 1711
01176 1712
01177 1713
01178 1714
01179 1715
01180 1716
01181 1717
01182 1718
01183 1719
01184 1720
01185 1721
01186 1722
01187 1723
01188 1724
01189 1725
01190 1726
01191 1727
01192 1728
01193 1729
01194 1730
01195 1731
01196 1732
01197 1733
01198 1734
01199 1735

```


0 FOR TRANSF TRANSF 09 MAY 77 228 1
 UNITAC 1108 FORTRAN 4 EXEC 11 LEVEL 25A - (EXEC8 LEVEL E12010010A)
 THIS COMPILATION WAS DONE ON 09 MAY 77 AT 22:09:57

SUBROUTINE TRANSF ENTRY POINT 000267

STORAGE USED: CODE(11) 0001071 DATA(0) 0000261 BLANK COMMON(2) 0000000

COMMON BLOCKS:

0003 TROCK 000046

EXTERNAL REFERENCES (BLOCK, NAME)

0004 NERR35

STORAGE ASSIGNMENT (BLOCK, TYPE, RELATIVE LOCATION, NAME)

0001 000021 1126 0003 000018 FETVCS 0003 000002 FLOINF 0000 000002 INJPS 0000 1 000000 IT
 0000 1 000001 JSAMP 0003 1 000003 NOFEAT 0000 000000 OUT(M) 0000 1 000002 LCONB

00101 10 SUBROUTINE TRANSF TRAN0001
 00102 20 (AT, WHAT, IDATA, TOP, IL, K, LCONB, NSAMP, BIAS) TRAN0002
 00103 30 C IMPLICIT INTEGER (A-Z) TRAN0003
 00104 40 REAL Z(116), BNAT(400), BIAS(16) TRAN0004
 00105 50 INCLUDE COMMON9, LIST TRAN0005
 00106 60 C DATA TRANSFORMATION COMMON BLOCK TRAN0006
 00107 60 COMMON/INLCAT/INTENT,NOFEAT,FLOINF(16), FETVLC(30)

ORIGINAL PAGE 16
 OF POOR QUALITY

APPENDIX C
VERIFICATION RUNS

TEST RUN 1

LYNDON B. JOHNSON SPACE CENTER
HOUSTON, TEXAS

25 APR 77

SDATA-TR

CURRENT
B-MATR
PLVOUT
DATAFI
FURNAT
BLUJ
WLOZ
DATE
CLND

... SAMPLE RUN NO. 1 ...
CARDS
UNIT = 3 FILE=1
OUTPUT = UNIV
DATA TRANSFORMATION PROCESSOR --- SAMPLE RUN
FLIGHT LINE C-1 DATA
JAN 12.1977

ORIGINAL PAGE IS
OF POOR QUALITY

DATA TRANSFORMATION PROCESSOR --- SAMPLE RUN
 FLIGHT LINE C-1 DATA
 ... SAMPLE RUN NO. 1 ...

JAN 12, 1977

LINEAR TRANSFORMATION (B) MATRIX

NO. LINEAR COMB. = 2
 NO. CHANNELS = 4

| LINE, CHB. | CHI 1) | CHI 2) | CHI 3) | CHI 4) |
|------------|----------|----------|----------|----------|
| 1 | .1000*01 | .0000 | .0000 | .0000 |
| 2 | .0000 | .0000*01 | .0000 | .0000 |
| 3 | .0000 | .0000 | .1000*31 | .0000 |
| 4 | .0000 | .0000 | .0000 | .1000*01 |

INPUT IMAGE DATA TAPE INFORMATION

FORMAT CHANNELS LANSYS 2
 NO. OF CHANNELS 12
 NO. OF PIXELS/LINE 228
 FIRST SCAN LINE NO. 1
 FIRST PIXEL REFERENCE PT 1

ORIGINAL PAGE IS
 OF POOR QUALITY

FIELDNAME NO. OF SAMPLE LINE VERTICES(SAMPLE LINE) 1 1 90. 90) 1 14 90)

• OUTPUT FILE 1 •

... TRANSFORMED VALUES NOT RESEALED ...

TRANSFORMED MINIMUMS, COMPONENTS 1-4 ...

103.00 95.00 149.00 176.00

TRANSFORMED MAXIMUMS, COMPONENTS 1-4 ...

194.00 211.00 210.00 210.00

TRANSFORMED VALUE BIAS, COMPONENTS 1-4 ...

.00 .00 .00 .00

NO. OF TRANSFORMED VALUES LESS THAN 0 (SET = 0) :

COMPONENT 1... 0 VALUES
COMPONENT 2... 0 VALUES
COMPONENT 3... 0 VALUES
COMPONENT 4... 0 VALUES

NO. OF TRANSFORMED VALUES GREATER THAN 255 (SET = 255) :

COMPONENT 1... 0 VALUES
COMPONENT 2... 0 VALUES
COMPONENT 3... 0 VALUES
COMPONENT 4... 0 VALUES

NO. OF LOWER TAIL POINTS REJECTED (SET = 0 FOR OUTPUT) TO SATISFY .05 CUT-OFF, COMPONENTS 1-4 ...

0 0 0 0

ORIGINAL PAGE IS
OF POOR QUALITY

NO. OF UPPER TAIL POINTS REJECTED (SET = 255 FOR OUTPUT) TO SATISFY .05 CUT-OFF. COMPONENTS 1 - 0 0 0 0

*** FINAL OUTPUT TRANSFORMED VALUES, CENTRAL 100 % OF DISTRIBUTION :

MINIMUMS. COMPONENTS 1 - 4 ***

103.00 95.00 199.00 196.00

MAXIMUMS. COMPONENTS 1 - 4 ***

194.00 211.00 218.00 210.00


JAN 12, 1977

DATA TRANSFORMATION PROCESSOR --- SAMPLE NUM
FLIGHT LINE C-1 DATA


... SAMPLE RUN NO. 1 ...

DATA IN

EACH * REPRESENTS 135 POINTS.



EACH * REPRESENTS 121 POINTS.




JAN 12, 1977

DATA TRANSFORMATION PROCESSOR --- SAMPLE MUN
FLIGHT LINE C-1 DATA


... SAMPLE MUN NO. 1 ...

DATA TR

EACH • REPRESENTS 100 POINT(S).



EACH • REPRESENTS 176 POINT(S).



ORIGINAL PAGE IS
OF POOR QUALITY

...SDATA-TR COMPLETED ...

TIME FOR DATA-TRANSFORMATION .356

26 APR 77

LYNDON B. JOHNSON SPACE CENTER
HOUSTON, TEXAS

TEST RUN 2

SDATA-IR

CUMHCH
HED1
HED2
R-MATR
PLHOUT
BIAS
DATAFI
GENDC

... SAMPLE RUN NO. 2 TEST RUN 2 DATATR
CI FLIGHT LINE

CARDS

0.0 : 100.0
0.0 : -100.0
FILE : 1.0 UNIT : 3

ORIGINAL PAGE IS
OF POOR QUALITY

26 APR 77

TEST RUN 7 DATA
C3 FLIGHT LINE

... SAMPLE RUN NO. 7 ...

LINEAR TRANSFORMATION (8) MATRIX

NO. LINEAR COORD. = 3
NO. CHANNELS = 4

| LIN. COORD. | CHI 1) | CHI 2) | CHI 3) | CHI 4) |
|-------------|----------|----------|----------|----------|
| 1 | .1000*01 | .0000 | .0000 | .0000 |
| 2 | .0000 | .1000*01 | .0000 | .0000 |
| 3 | .0000 | .0000 | .1000*01 | .0000 |
| 4 | .0000 | .0000 | .0000 | .1000*01 |

INPUT IMAGE DATA TAPE INFORMATION

FORMAT LARSYS 2
NO. OF CHANNELS 12
NO. OF PIXELS/LINE 228
FIRST SCAN LINE NO. 1
FIRST PIXEL REFERENCE PT 1

ORIGINAL PAGE IS
OF POOR QUALITY

[illegible]

• OUTPUT FILE ! •

... TRANSFORMED VALUES NOT RECALCULATED ...

TRANSFORMED MINIMUMS, COMPONENTS 1-4...

| | | | |
|--------|--------|--------|-------|
| 103.00 | 195.00 | 144.00 | 46.00 |
|--------|--------|--------|-------|

TRANSFORMED MAXIMUMS, COMPONENTS 1-4 ...

| | | | |
|--------|--------|--------|--------|
| 197.00 | 311.00 | 210.00 | 110.00 |
|--------|--------|--------|--------|

TRANSFORMED VALUE BIAS, COMPONENTS 1 - .4 1

| | | | |
|--------|--------|--------|--------|
| 100.00 | 100.00 | 100.00 | 100.00 |
|--------|--------|--------|--------|

NO. OF TRANSFORMED VALUES LESS THAN 0 1 SET = 0 1 1

| | | | |
|-----------|------|---|--------|
| COMPONENT | 1... | 0 | VALUES |
| COMPONENT | 2... | 0 | VALUES |
| COMPONENT | 3... | 0 | VALUES |
| COMPONENT | 4... | 0 | VALUES |

NO. OF TRANSFORMED VALUES GREATER THAN 255 (SET = 255) !

| | | | |
|-----------|------|------|--------|
| COMPONENT | 1.00 | 0 | VALUES |
| COMPONENT | 2.00 | 7990 | VALUES |
| COMPONENT | 3.00 | 0 | VALUES |
| COMPONENT | 4.00 | 0 | VALUES |

| NO. OF LOWER TAIL POINTS REJECTED | (SET = 0 FOR OUTPUT) TO SATISFY | 0.5 CUT-OFF, COMPONENTS |
|-----------------------------------|-----------------------------------|-------------------------|
| 1 | 0.0000 | 0.0000 |
| 2 | 0.0000 | 0.0000 |
| 3 | 0.0000 | 0.0000 |
| 4 | 0.0000 | 0.0000 |
| 5 | 0.0000 | 0.0000 |
| 6 | 0.0000 | 0.0000 |
| 7 | 0.0000 | 0.0000 |
| 8 | 0.0000 | 0.0000 |
| 9 | 0.0000 | 0.0000 |
| 10 | 0.0000 | 0.0000 |
| 11 | 0.0000 | 0.0000 |
| 12 | 0.0000 | 0.0000 |
| 13 | 0.0000 | 0.0000 |
| 14 | 0.0000 | 0.0000 |
| 15 | 0.0000 | 0.0000 |
| 16 | 0.0000 | 0.0000 |
| 17 | 0.0000 | 0.0000 |
| 18 | 0.0000 | 0.0000 |
| 19 | 0.0000 | 0.0000 |
| 20 | 0.0000 | 0.0000 |
| 21 | 0.0000 | 0.0000 |
| 22 | 0.0000 | 0.0000 |
| 23 | 0.0000 | 0.0000 |
| 24 | 0.0000 | 0.0000 |
| 25 | 0.0000 | 0.0000 |
| 26 | 0.0000 | 0.0000 |
| 27 | 0.0000 | 0.0000 |
| 28 | 0.0000 | 0.0000 |
| 29 | 0.0000 | 0.0000 |
| 30 | 0.0000 | 0.0000 |
| 31 | 0.0000 | 0.0000 |
| 32 | 0.0000 | 0.0000 |
| 33 | 0.0000 | 0.0000 |
| 34 | 0.0000 | 0.0000 |
| 35 | 0.0000 | 0.0000 |
| 36 | 0.0000 | 0.0000 |
| 37 | 0.0000 | 0.0000 |
| 38 | 0.0000 | 0.0000 |
| 39 | 0.0000 | 0.0000 |
| 40 | 0.0000 | 0.0000 |
| 41 | 0.0000 | 0.0000 |
| 42 | 0.0000 | 0.0000 |
| 43 | 0.0000 | 0.0000 |
| 44 | 0.0000 | 0.0000 |
| 45 | 0.0000 | 0.0000 |
| 46 | 0.0000 | 0.0000 |
| 47 | 0.0000 | 0.0000 |
| 48 | 0.0000 | 0.0000 |
| 49 | 0.0000 | 0.0000 |
| 50 | 0.0000 | 0.0000 |
| 51 | 0.0000 | 0.0000 |
| 52 | 0.0000 | 0.0000 |
| 53 | 0.0000 | 0.0000 |
| 54 | 0.0000 | 0.0000 |
| 55 | 0.0000 | 0.0000 |
| 56 | 0.0000 | 0.0000 |
| 57 | 0.0000 | 0.0000 |
| 58 | 0.0000 | 0.0000 |
| 59 | 0.0000 | 0.0000 |
| 60 | 0.0000 | 0.0000 |
| 61 | 0.0000 | 0.0000 |
| 62 | 0.0000 | 0.0000 |
| 63 | 0.0000 | 0.0000 |
| 64 | 0.0000 | 0.0000 |
| 65 | 0.0000 | 0.0000 |
| 66 | 0.0000 | 0.0000 |
| 67 | 0.0000 | 0.0000 |
| 68 | 0.0000 | 0.0000 |
| 69 | 0.0000 | 0.0000 |
| 70 | 0.0000 | 0.0000 |
| 71 | 0.0000 | 0.0000 |
| 72 | 0.0000 | 0.0000 |
| 73 | 0.0000 | 0.0000 |
| 74 | 0.0000 | 0.0000 |
| 75 | 0.0000 | 0.0000 |
| 76 | 0.0000 | 0.0000 |
| 77 | 0.0000 | 0.0000 |
| 78 | 0.0000 | 0.0000 |
| 79 | 0.0000 | 0.0000 |
| 80 | 0.0000 | 0.0000 |
| 81 | 0.0000 | 0.0000 |
| 82 | 0.0000 | 0.0000 |
| 83 | 0.0000 | 0.0000 |
| 84 | 0.0000 | 0.0000 |
| 85 | 0.0000 | 0.0000 |
| 86 | 0.0000 | 0.0000 |
| 87 | 0.0000 | 0.0000 |
| 88 | 0.0000 | 0.0000 |
| 89 | 0.0000 | 0.0000 |
| 90 | 0.0000 | 0.0000 |
| 91 | 0.0000 | 0.0000 |
| 92 | 0.0000 | 0.0000 |
| 93 | 0.0000 | 0.0000 |
| 94 | 0.0000 | 0.0000 |
| 95 | 0.0000 | 0.0000 |
| 96 | 0.0000 | 0.0000 |
| 97 | 0.0000 | 0.0000 |
| 98 | 0.0000 | 0.0000 |
| 99 | 0.0000 | 0.0000 |
| 100 | 0.0000 | 0.0000 |

0
0
-
A

[illegible]

0
.
0
0
0

ORIGINAL PAGE IS
OF POOR QUALITY

.... FINAL OUTPUT TRANSFORMED VALUES, CENTRAL 100 % OF DISTRIBUTION :

MINIMUMS, COMPONENTS 1 - 9 ...

| | | | |
|--------|--------|--------|-------|
| 103.00 | 195.00 | 149.00 | 96.00 |
|--------|--------|--------|-------|

MAXIMUMS, COMPONENTS 1 - 9 ...

| | | | |
|--------|--------|--------|--------|
| 197.00 | 255.00 | 210.00 | 110.00 |
|--------|--------|--------|--------|


26 APR 77

TEST RUN - DATA
C1 FLIGHT LINE


... SAMPLE RUN NO. 7 ...

DATA TR

EACH * REPRESENTS 135 POINT(S).



EACH * REPRESENTS 531 POINT(S).



25 APR 77

TEST RUN NO. DATA
CI FLIGHT LINE

... SAMPLE RUN NO. 7 ...

DATA IN

EACH REPRESENTS 100 POINT(S).

2700
2500
2300
2100
1900
1700
1500
1300
1100
900
700
500
300
100

255
230
204
179
153
126
102
77
51
26
0

EACH REPRESENTS 100 POINT(S).

2700
2500
2300
2100
1900
1700
1500
1300
1100
900
700
500
300
100

255
230
204
179
153
126
102
77
51
26
0

... DATA-TR COMPLETED ...

TIME FOR DATA-TRANSFORMATION .399

ORIGINAL PAGE IS
OF POOR QUALITY

TEST RUN 3

LYNDON B. JOHNSON SPACE CENTER
HOUSTON, TEXAS

26 APR 77

SDATA-TR

CUMMEN
MDI
MDZ
DATE
N-MATR
NLSCL
MODUL
SUNCLA
STATFI
DATAFI
OPTION
LAM
PMDUT
BIAS
FUKMAT
ELMO

... SAMPLE RUN NO. 2 ...
DATA TRANSFORMATION PROCESSOR
FLC-1 DATA
JAN 12.1177
CARUS
FILE
1. 2. 3. 4. 5. 6. 7. 8. 9. 10. 11. 12. 13
UNIT-1 : FILE-1
FILL-1 : UNIT-3
URIG. TRANSF. PUNCH
2
0.0 : 5.0.0.2. 0.0 : 0.0.0.0
U.0 : 3. 0.0. 0.0
OUTPUT = U

DATA TRANSFORMATION PROCESSOR

JAN 12.1977

... ORIGINAL STATISTICS ...

SUBCLASS MOMNO1
MEAN 165.84
COVARIANCE MATRIX

| | | |
|--------|--------|--------|
| 171.16 | 190.76 | 169.32 |
| 6.56 | | |
| 6.40 | 9.22 | |
| 3.79 | 3.87 | 2.94 |
| 5.30 | 6.32 | 3.45 |
| | | 5.64 |

SUBCLASS MOMNO2
MEAN 172.04
COVARIANCE MATRIX

| | | |
|--------|--------|--------|
| 176.99 | 194.45 | 193.79 |
| 64.91 | | |
| 68.67 | 80.99 | |
| 45.66 | 50.00 | 34.29 |
| 46.76 | 53.88 | 34.38 |
| | | 38.64 |

DATA TRANSFORMATION PROCESSOR
PL C-1 DATA

JAN 12, 1977

... ORIGINAL STATISTICS ...

SUBCLASS WOM003
MEAN 172.99 177.85 195.47 194.72
COVARIANCE MATRIX
5.76
4.29 9.18
4.05 4.00 4.48
3.11 3.99 2.93 4.17

SUBCLASS WOM004
MEAN 171.46 175.75 193.34 191.79
COVARIANCE MATRIX
172.00
145.28 379.47
136.12 131.08 113.54
80.70 201.04 75.37 137.35

ORIGINAL TABLE
OF POOR QUALITY

C-1

DATA TRANSFORMATION PROCESSOR
FL C-1 DATA

JAN 12, 1977

... ORIGINAL STATISTICS ...

SUBCLASS NONWOS
MEAN 171.80
COVARIANCE MATRIX

176.47 193.95 193.15

8.96

8.15

10.47

4.63

4.93

3.94

5.48

5.56

3.05

4.62

SUBCLASS NONNO1
MEAN 161.12
COVARIANCE MATRIX

165.64 107.14 185.17

186.76

211.17

270.14

136.70

158.82

102.31

146.34

180.51

109.79

132.19

83

JAN 12.197

DATA TRANSFORMATION PROCESSOR
PL C-1 DATA

... ORIGINAL STATISTICS ...

SUBCLASS NONNO2
MEAN 171.55
COVARIANCE MATRIX

| | | |
|--------|--------|--------|
| 175.94 | 193.74 | 192.60 |
| 40.86 | | |
| 39.18 | 58.52 | |
| 28.71 | 29.46 | 21.91 |
| 26.24 | 34.08 | 19.91 |
| | | 26.87 |

SUBCLASS NONNO3
MEAN 171.02
COVARIANCE MATRIX

| | | |
|--------|--------|--------|
| 175.56 | 193.67 | 192.92 |
| 24.08 | | |
| 25.75 | 33.58 | |
| 17.57 | 19.96 | 14.87 |
| 19.30 | 22.97 | 15.19 |
| | | 10.36 |

ORIGINAL PAGE IS
OF POOR QUALITY

JAN 12.1971

DATA TRANSFORMATION PROCESSOR
FL C-1 DATA

... ORIGINAL STATISTICS ...

SUBCLASS NONH04
MEAN 173.69 177.90 194.75 193.01
COVARIANCE MATRIX

| | | | |
|-------|-------|-------|-------|
| 36.22 | | | |
| 35.95 | 51.67 | | |
| 23.69 | 26.76 | 19.10 | |
| 22.00 | 30.32 | 16.05 | 23.05 |

SUBCLASS NONH05
MEAN 174.06 178.54 195.63 194.93
COVARIANCE MATRIX

| | | | |
|-------|-------|------|-------|
| 19.77 | | | |
| 18.32 | 21.82 | | |
| 12.45 | 12.65 | 9.07 | |
| 12.57 | 13.66 | 9.05 | 11.30 |

DATA TRANSFORMATION PROCESSOR
FL C-1 DATA

JAN 12, 1977

... ORIGINAL STATISTICS ...

SUBCLASS NONNO6
MEAN 167.27
COVARIANCE MATRIX
2.89
174.40 192.77 192.00
.72 2.04
.86 .48 2.05
.41 .45 .14 .55

SUBCLASS NONNO7
MEAN 171.47
COVARIANCE MATRIX
21.87
20.99 22.70
17.81 17.82 16.25
18.00 18.29 15.65 16.71

JAN 12.197

DATA TRANSFORMATION PROCESSOR
PL C-1 DATA

... ORIGINAL STATISTICS ...

SUBCLASS NONNOB 170.70 190.37 100.57
MEAN 166.50
COVARIANCE MATRIX

1.78

.53 3.09

.36 .14 1.03

-.05 -.11 -.04 .32

DATA TRANSFORMATION PROCESSOR
FL C-1 DATA

JAN 12, 1977

... SAMPLE RUN NO. 2 ...

LINEAR TRANSFORMATION (B) MATRIX

NO. LINEAR COMB. = 4
NO. CHANNELS = 4

| LIN. COMB. | CH(1) | CH(2) | CH(3) | CH(4) |
|------------|----------|----------|----------|----------|
| 1 | .1000*01 | .0000 | .0000 | .0000 |
| 2 | .0000 | .1000*01 | .0000 | .0000 |
| 3 | .0000 | .0000 | .1000*01 | .0000 |
| 4 | .0000 | .0000 | .0000 | .1000*01 |

DATA TRANSFORMATION PROCESSOR

JAN 12, 1977

PL C-1 DATA

... TRANSFORMED STATISTICS ...

SUBCLASS #00001
 MEAN 165.84
 COVARIANCE MATRIX
 6.54
 6.40 9.22
 3.79 3.87 2.94
 5.30 6.32 3.45 5.64

SUBCLASS #00002
 MEAN 172.06
 COVARIANCE MATRIX
 64.91
 60.67 80.99
 45.66 50.00 34.29
 46.76 53.88 34.38 38.69

ORIGINAL PAGE IS
 OF POOR QUALITY

DATA TRANSFORMATION PROCESSOR
FL C-1 DATA

JAN 12, 1977

... TRANSFORMED STATISTICS ...

SUBCLASS W00003
MEAN 172.99 177.65 195.47 199.72
COVARIANCE MATRIX
6.76
9.10
9.05 9.40
3.11 3.99 2.93 4.17

SUBCLASS W00004
MEAN 171.46 175.75 193.34 191.79
COVARIANCE MATRIX
172.00
145.28 379.47
136.12 131.08 113.54
80.70 201.04 75.37 137.35

JAN 12, 1977

DATA TRANSFORMATION PROCESSOR
FL C-1 DATA

• TRANSFORMED STATISTICS ...

NONN04
173.69 177.90 194.75 193.01
E MATRIX
36.22
35.95 51.67
23.69 26.76 19.10
22.00 30.32 18.05 23.05

NONN05
174.06 178.54 195.63 191.93
E MATRIX
19.77
18.32 21.02
12.45 12.65 9.07
12.57 13.46 9.05 11.30

DATA TRANSFORMATION PROCESSOR
FL C-1 DATA

JAN 12, 1977

... TRANSFORMED STATISTICS ...

SUBCLASS NONNO6
MEAN 187.27 174.90 192.77 192.00
COVARIANCE MATRIX

2.89
.72 2.09
.86 .98 2.05
.91 .95 .14 .55

SUBCLASS NONNO7
MEAN 171.97 175.71 193.52 192.67
COVARIANCE MATRIX

21.87
20.99 23.70
17.81 17.82 16.25
18.00 18.29 15.65 16.71

JAN 12.1977

DATA TRANSFORMATION PROCESSOR
PL C-1 DATA

... TRANSFORMED STATISTICS ...

SUBCLASS MONNOG 170.90 190.37 100.57
MEAN 166.50
COVARIANCE MATRIX

1.78
-53 3.89
-36 .14 1.03
-05 -.11 -.04 .32

INPUT IMAGE DATA TAPE INFORMATION

FORMAT LARSYS 2
NO. OF CHANNELS 12
NO. OF PIXELS/LINE 278
FIRST SCAN LINE NO. 1
FIRST PIXEL REFERENCE PT 1

FILENAME VERTICES SAMPLE LINE VERTICES(SAMPLE.LINE)

11 (90. 90) 1 10. 90)

• OUTPUT FILE 1 •

... TRANSFORMED VALUES RESCALED TO A RANGE 0 - 255 ...
(STATISTICS METHOD)

... ORIGINAL TRANSFORMED DATA RANGE ...

| MIN | MAX | (BIAS) |
|----------|----------|-----------|
| 103.0000 | 194.0000 | (.0000) |
| 95.0000 | 211.0000 | (.0000) |
| 149.0000 | 210.0000 | (.0000) |
| 146.0000 | 210.0000 | (.0000) |

... TRANSFORMED DATA RANGE, AFTER APPLICATION OF PEROUT ...

MIN MAX CON = 255/(MAX-MIN)

| | | |
|----------|----------|---------|
| 163.2390 | 182.9126 | 17.5103 |
| 165.5431 | 188.6274 | 17.4789 |
| 166.6072 | 203.6274 | 17.8333 |
| 164.7246 | 203.6389 | 16.5234 |

ORIGINAL PAGE IS
ON FILE IN 111


JAN 12.1977

DATA TRANSFORMATION PROCESSOR
PL C-1 DATA

... SAMPLE RUN NO. 2...


DATA 1R

EACH • REPRESENTS 57 POINT(S).



ORIGINAL PAGE IS
OF POOR QUALITY

EACH • REPRESENTS 51 POINT(S).




DATA TRANSFORMATION PROCESSOR FL C-1 DATA

JAN 12.1977


... SAMPLE RUN NO. 2 ...

DATA TR

EACH • REPRESENTS 68 POINT(S).



EACH • REPRESENTS 67 POINT(S).



SCALING PARAMETERS USED ON TRANSFORMED VALUES. OUTPUT FILE

| COMPONENT | MINIMUM | MAXIMUM | SCALE FACTOR (CON) |
|-----------|---------|---------|--------------------|
| 1 | 163.340 | 180.914 | 19.510 |
| 2 | 165.544 | 166.029 | 12.478 |
| 3 | 166.604 | 203.927 | 17.803 |
| 4 | 184.725 | 200.639 | 16.023 |

... SDATA-IR COMPLETED ...

TIME FOR DATA-TRANSFORMATION .901

TEST RUN 4

LYNDON B. JOHNSON SPACE CENTER
HOUSTON, TEXAS

25 APR 77

SDATA-TR

CUMMEN
HED1
HED2
H-MATR
RESCAL
OPTION
PLHOUT
DATAF
PUMMA
SEND

... SAMPLE RUN NO. 5
SAMPLE RUN - DATA TR
FLY LINE C-1

CARDS

SCAFAC 1 14.510 163.370 1 : 12.448 165.544 1 :
SCAFAC 1 17.803 186.604 1 : 16.023 188.726 1 :
U-3 F=1
OUTPUT = U

ORIGINAL FILE
OF POOR QUALITY

SAMPLE RUN - DATA TR
FLT LINE C-1

26 APR 77

... SAMPLE RUN NO. 5 ...

LINEAR TRANSFORMATION (B) MATRIX

NO. LINEAR COMB. = 4
NO. CHANNELS

| LIN. COMB. | CHI 1) | CHI 2) | CHI 3) | CHI 4) |
|------------|----------|----------|----------|----------|
| 1 | .1000*01 | .0000 | .0000 | .0000 |
| 2 | .0000 | .1000*01 | .0000 | .0000 |
| 3 | .0000 | .0000 | .1000*01 | .0000 |
| 4 | .0000 | .0000 | .0000 | .1000*01 |

INPUT IMAGE DATA TAPE INFORMATION

FORMAT LARSYS 2
NO. OF CHANNELS 220
NO. OF PIXELS/LINE 220
FIRST SCAN LINE NO. 1
FIRST PIXEL REFERENCE PT 1

FIELDNAME NO. OF SAMPLE LINE
 (C-1) VERTICES INC INC VERTICESAMPLE LINE
 (90. 90) (1. 90)

• OUTPUT FILE 1 •

... TRANSFORMED VALUES RESEALED TO A RANGE 0 - 255 ...
 (INPUT SCALING PARAMETERS)

... ORIGINAL TRANSFORMED DATA RANGE ...

| MIN | MAX | (DIAS) |
|----------|----------|-----------|
| 103.0000 | 194.0000 | (.0000) |
| 95.0000 | 211.0000 | (.0000) |
| 149.0000 | 210.0000 | (.0000) |
| 146.0000 | 210.0000 | (.0000) |

... TRANSFORMED DATA RANGE, AFTER APPLICATION OF PEROUT ...

MIN MAX CUN = 255/(MAX-MIN)

| | | |
|----------|----------|---------|
| 103.2400 | 100.9191 | 14.5100 |
| 105.5440 | 100.9272 | 13.4480 |
| 106.8040 | 200.9274 | 13.8030 |
| 104.7250 | 200.6394 | 16.0230 |

ORIGINAL RANGE
 OF POOR QUALITY


25 APR 77

SAMPLE NUM - DATA TR
FLY LINE C-1


... SAMPLE RUN NO. 5 ...

DATA TR

EACH * REPRESENTS S7 POINT(S).



EACH * REPRESENTS S1 POINT(S).



C-56


25 APR 77

SAMPLE RUN - DATA TR
PLT LINE C-1


... SAMPLE RUN NO. 5 ...

DATA TR

EACH • REPRESENTS 60 POINT(S).



EACH • REPRESENTS 67 POINT(S).



SCALING PARAMETERS USED ON TRANSFORMED VALUES, OUTPUT FILE 1

| COMPONENT | MINIMUM | MAXIMUM | SCALE FACTOR (CON 1) |
|-------------|---------|---------|----------------------|
| COMPONENT 1 | 103.340 | 180.914 | 14.510 |
| COMPONENT 2 | 105.549 | 186.029 | 13.448 |
| COMPONENT 3 | 102.604 | 200.927 | 13.803 |
| COMPONENT 4 | 104.725 | 200.640 | 16.023 |

*** DATA-TR COMPLETED ***

TIME FOR DATA-TRANSFORMATION .370

ORIGINAL COPY
OF POOR QUALITY

6-88

TEST RUN 5

LYNDON B. JOHNSON SPACE CENTER
HOUSTON, TEXAS

26 APR 77

SDATA-IR

CUMMEN
MLDI
DATE
R-MAIR
MAIRPI
MAIRPI
PLMUUY
RESCAL
DATAFI
OLNDS

... SAMPLE RUN NO. 6 ...
DATA-IR PROCESSOR
C-I FLIGHT LINE

12 JAN 77
CARS
255.255.255.255.255.255.255.255.255.255.255
255.255.255.255.255.255.255.255.255.255.255
255.255.255.255.255.255.255.255.255.255.255
S

U = 3 . F = 1

PA-7M PHOTOMETER

12 JAN. 1977

... SAMPLE RUN NO. 6 ...

LINEAR TRANSFORMATION (M) MATRIX

NO. LINEAR COMB. = 2
NO. CHANNELS

| LIN. COMB. | CHI 1) | CHI 2) | CHI 3) | CHI 4) |
|------------|----------|----------|----------|----------|
| 1 | .1000*01 | .0000 | .0000 | .0000 |
| 2 | .0000 | .1000*01 | .0000 | .0000 |
| 3 | .0000 | .0000 | .1000*01 | .0000 |
| 4 | .0000 | .0000 | .0000 | .1000*01 |

INPUT IMAGE DATA TAPE INFORMATION

FORMAT CHANNELS LANSYS 2
NO. OF CHANNELS 12
NO. OF PIXELS/LINE 228
FIRST SCAN LINE NO. 1
FIRST PIXEL REFERENCE PT 1

FIELDNAME NO. OF SAMPLE LINE VERTICESISAMPLE LINE
 C-1 1 1 90. 90) (1. 90)

• OUTPUT FILE 1 •

*** TRANSFORMED VALUES RESCALED TO A RANGE 0 - 255 ***
 (HISTOGRAM METHOD)

*** ORIGINAL TRANSFORMED DATA RANGE ***

| MIN | MAX | (BIAS) |
|----------|----------|-----------|
| 103.0000 | 194.0000 | (.0000) |
| 95.0000 | 211.0000 | (.0000) |
| 149.0000 | 210.0000 | (.0000) |
| 146.0000 | 210.0000 | (.0000) |

*** TRANSFORMED DATA RANGE, AFTER APPLICATION OF PEROUT ***

| MIN | MAX | CUN = 255/(MAX-MIN) |
|----------|----------|---------------------|
| 140.6500 | 181.9500 | 12.5900 |
| 138.1000 | 186.7000 | 8.3333 |
| 191.9500 | 201.4500 | 12.5500 |
| 178.5000 | 291.4500 | 11.1111 |


DATA-TR PROCESSOR
C-1 FLIGHT LINE

12 JAN. 1977


... SAMPLE RUN NO. 6 ...

DATA TR

EACH • REPRESENTS 57 POINT(S).



EACH • REPRESENTS 51 POINT(S).



DATA-TR PROCESSOR
C-1 FLIGHT LINE
QUALITY


12 JAN. 1977

DATA-TR PRUCESOR
C-1 FLIGHT LINE


... SAMPLE NUM NO. 6 ...

DATA 17

EACH * REPRESENTS 40 POINT(S).



EACH * REPRESENTS 47 POINT(S).



SCALING PARAMETERS USED ON TRANSFORMED VALUES, OUTPUT FILE 1

| COMPONENT | 1 | 2 | 3 | 4 |
|----------------------|---------|---------|---------|---------|
| MINIMUM | 140.650 | 158.100 | 181.050 | 178.500 |
| MAXIMUM | 181.950 | 198.700 | 201.450 | 201.450 |
| SCALE FACTOR (COM) | 12.500 | 4.333 | 12.500 | 11.111 |

... SDATA-TR COMPLETED ...

TIME FOR DATA-TRANSFORMATION .534

ORIGINAL PAGE IS
OF POOR QUALITY